



# **Dr.WEB**

Industrial for UNIX File Servers

## **Administrator Manual**



© Doctor Web, 2024. All rights reserved

This document is intended for information and reference purposes regarding the Dr.Web software discussed herein. This document is not a basis for exhaustive conclusions about the presence or absence of any functional and/or technical features in Dr.Web software and cannot be used to determine whether Dr.Web software meets any requirements, technical specifications and/or parameters, and other third-party documents.

This document is the property of Doctor Web and may be used solely for the personal purposes of the purchaser of the product. No part of this document may be reproduced, published or transmitted in any form or by any means, without proper attribution, for any purpose other than the purchaser's personal use.

### **Trademarks**

Dr.Web, SplDer Mail, SplDer Guard, CureIt!, CureNet!, AV-Desk, KATANA and the Dr.WEB logo are trademarks and registered trademarks of Doctor Web in Russia and/or other countries. Other trademarks, registered trademarks and company names used in this document are the property of their respective owners.

### **Disclaimer**

In no event shall Doctor Web and its resellers or distributors be liable for any errors or omissions, or for any loss of profit or any other damage caused or alleged to be caused directly or indirectly by this document, or by the use of or inability to use the information contained in this document.

**Dr.Web Industrial for UNIX File Servers**  
**Version 11.1**  
**Administrator Manual**  
**6/5/2024**

Doctor Web Head Office

2-12A, 3rd str. Yamskogo polya, Moscow, Russia, 125124

Website: <https://www.drweb.com/>

Phone: +7 (495) 789-45-87

Refer to the official website for regional and international office information.

## **Doctor Web**

Doctor Web develops and distributes Dr.Web information security solutions that provide effective protection against malicious software and spam.

Doctor Web customers include home users around the world, government agencies, small businesses, and nationwide corporations.

Since 1992, Dr.Web anti-virus solutions have been known for their continuous excellence in malware detection and compliance with international information security standards.

The state certificates and awards received by Dr.Web solutions, as well as the worldwide use of our products, are the best evidence of exceptional trust in the company products.

**We thank all our customers for their support and devotion to Dr.Web products!**



# Table of Contents

<b>Introduction</b>	<b>8</b>
<b>Conventions and Abbreviations</b>	<b>9</b>
<b>About this Product</b>	<b>10</b>
<b>Dr.Web Industrial for UNIX File Servers Main Functions</b>	<b>10</b>
<b>Structure of Dr.Web Industrial for UNIX File Servers</b>	<b>12</b>
<b>Placing in Quarantine</b>	<b>19</b>
<b>File Permissions and Privileges</b>	<b>20</b>
<b>Operation Modes</b>	<b>21</b>
<b>System Requirements and Compatibility</b>	<b>24</b>
<b>Licensing</b>	<b>28</b>
<b>Installing and Uninstalling</b>	<b>29</b>
<b>Installing Dr.Web Industrial for UNIX File Servers</b>	<b>30</b>
Installing the Universal Package	31
Installing from the Command Line	33
Installing from the Repository	33
<b>Upgrading Dr.Web Industrial for UNIX File Servers</b>	<b>37</b>
Updating Packages and Components	37
Upgrading to a New Product Version	38
Database Update without Internet Connection	41
<b>Uninstalling Dr.Web Industrial for UNIX File Servers</b>	<b>42</b>
Uninstalling the Universal Package	42
Uninstalling from the Command Line	43
Uninstallation of Dr.Web Industrial for UNIX File Servers Installed from the Repository	43
<b>Additional Information</b>	<b>47</b>
Dr.Web Industrial for UNIX File Servers Packages and Files	47
Custom Component Installation and Uninstallation	49
<b>Configuring Security Subsystems</b>	<b>54</b>
Configuring SELinux Security Policies	55
Configuring the Launch in the CSE Mode (Astra Linux SE 1.6 and 1.7)	58
<b>Getting Started</b>	<b>59</b>
<b>Registration and Activation</b>	<b>59</b>
<b>Testing Product Operation</b>	<b>62</b>



<b>File System Monitoring Setting</b>	<b>63</b>
<b>Integration with Samba File Server</b>	<b>65</b>
<b>Brief Instructions</b>	<b>69</b>
<b>Dr.Web Industrial for UNIX File Servers Components</b>	<b>74</b>
<b>Dr.Web ConfigD</b>	<b>74</b>
Operating Principles	74
Command-Line Arguments	76
Configuration Parameters	77
<b>Dr.Web Ctl</b>	<b>80</b>
Command-Line Call Format	82
Usage Examples	111
Configuration Parameters	115
<b>Dr.Web Web Management Interface</b>	<b>116</b>
Managing the Components	118
Threats Management	119
Managing the Settings	120
Managing the Centralized Protection	125
Scanning Local Files	126
<b>SplDer Guard</b>	<b>130</b>
Operating Principles	130
Command-Line Arguments	133
Configuration Parameters	134
<b>SplDer Guard for SMB</b>	<b>141</b>
Operating Principles	141
Command-Line Arguments	143
Configuration Parameters	144
Building the VFS SMB Module	150
<b>Dr.Web File Checker</b>	<b>153</b>
Operating Principles	153
Command-Line Arguments	154
Configuration Parameters	155
<b>Dr.Web Network Checker</b>	<b>157</b>
Operating Principles	157
Command-Line Arguments	158
Configuration Parameters	159
Creating the Scanning Cluster	164



<b>Dr.Web Scanning Engine</b>	<b>168</b>
Operating Principles	168
Command-Line Arguments	169
Configuration Parameters	172
<b>Dr.Web Updater</b>	<b>174</b>
Operating Principles	174
Command-Line Arguments	175
Configuration Parameters	176
<b>Dr.Web ES Agent</b>	<b>182</b>
Operating Principles	182
Command-Line Arguments	183
Configuration Parameters	183
<b>Dr.Web HTTPD</b>	<b>186</b>
Operating Principles	186
Command-Line Arguments	187
Configuration Parameters	188
Description of the HTTP API	191
<b>Dr.Web SNMPD</b>	<b>213</b>
Operating Principles	213
Command-Line Arguments	214
Configuration Parameters	215
Integration with SNMP Monitoring Systems	219
Dr.Web SNMP MIB	227
<b>Dr.Web MeshD</b>	<b>246</b>
Operating Principles	246
Command-Line Arguments	250
Configuration Parameters	250
<b>Dr.Web StatD</b>	<b>255</b>
Operating Principles	255
Command-Line Arguments	255
Configuration Parameters	256
<b>Appendices</b>	<b>258</b>
<b>Appendix A. Types of Computer Threats</b>	<b>258</b>
<b>Appendix B. Neutralizing Computer Threats</b>	<b>262</b>
<b>Appendix C. Technical Support</b>	<b>264</b>
<b>Appendix D. Dr.Web Industrial for UNIX File Servers Configuration File</b>	<b>266</b>



File Structure	266
Parameter Types	268
<b>Appendix E. Generating SSL certificates</b>	<b>271</b>
<b>Appendix F. Known Errors</b>	<b>274</b>
<b>Appendix G. List of Abbreviations</b>	<b>318</b>
<b>Index</b>	<b>320</b>



## Introduction

Thank you for purchasing the Dr.Web Industrial for UNIX File Servers solution. It offers reliable protection of your server from the spread of various types of [computer threats](#) by using the most advanced virus [detection and neutralization technologies](#). This improves the quality of services provided by the server.

This manual is intended to help administrators of the servers that run an UNIX OS-like, such as OS of the GNU/Linux family or FreeBSD, to install and use Dr.Web Industrial for UNIX File Servers.

### Convention for File Paths

Real paths to files and components depend on the operating system. The document uses the following conventions for directories:

- `<opt_dir>`—directory where main product files are located (including executable files and libraries);
- `<etc_dir>`—directory where the configuration file and a key file are located;
- `<var_dir>`—directory where supporting and temporary product files are located.

Real paths corresponding to the conventions in different operating systems are given in the table below.

OS Type	Convention	Real Path
GNU/Linux	<code>&lt;opt_dir&gt;</code>	<code>/opt/drweb.com</code>
	<code>&lt;etc_dir&gt;</code>	<code>/etc/opt/drweb.com</code>
	<code>&lt;var_dir&gt;</code>	<code>/var/opt/drweb.com</code>
FreeBSD	<code>&lt;opt_dir&gt;</code>	<code>/usr/local/libexec/drweb.com</code>
	<code>&lt;etc_dir&gt;</code>	<code>/usr/local/etc/drweb.com</code>
	<code>&lt;var_dir&gt;</code>	<code>/var/drweb.com</code>



For space considerations, examples use paths for GNU/Linux operating systems. In some places of the document, where it is possible, examples contain real paths for all of the operating systems.





## Conventions and Abbreviations

The following symbols and text conventions are used in this guide:

Convention	Comment
	An important note or instruction.
	A warning about possible errors or important notes that require special attention.
<i>Anti-virus network</i>	A new term or an emphasis on a term in descriptions.
<IP-address>	Placeholders.
<b>Save</b>	Names of buttons, windows, menu items and other program interface elements.
CTRL	Names of keyboard keys.
/home/user	Names of files and folders, code examples.
<a href="#">Appendix A</a>	Cross-references to document chapters or internal hyperlinks to webpages.



Command-line commands, entered using a keyboard (in the terminal or a terminal emulator), are marked with the command prompt character `$` or `#` in the current manual. The character indicates the privileges required for execution of the specified command. According to the standard convention for UNIX-based systems,

- `$`—indicates that the command can be executed with user rights.
- `#`—indicates that the command can be executed with superuser (usually *root*) privileges. To elevate the privileges, use `su` and `sudo` commands.

List of abbreviations is in section [Appendix G. List of Abbreviations](#).



## About this Product

### In this section

- [Function](#)
- [Dr.Web Industrial for UNIX File Servers Main Functions](#)
- [Structure of Dr.Web Industrial for UNIX File Servers](#)
- [Placing in Quarantine](#)
- [File Permissions and Privileges](#)
- [Operation Modes](#)

### Function

Dr.Web Industrial for UNIX File Servers is designed to protect file servers running under UNIX (GNU/Linux, and FreeBSD) from viruses and other types of any malicious software, as well as to prevent distribution of these threats developed for various platforms.

By default, Dr.Web Industrial for UNIX File Servers does not interfere with the operating system and only notifies the user of detected threats; this allows to use the anti-virus solution in an industrial infrastructure, in which emergency shutdown of machinery and outage are unacceptable.

Main components (scan engine and virus databases) are not only highly effective and resource-sparing, but also cross-platform, which lets Doctor Web specialists create reliable anti-virus solutions protecting computers and mobile devices under popular operating systems from threats that target different platforms. Currently, along with Dr.Web Industrial for UNIX File Servers, Doctor Web offers anti-virus solutions for both UNIX-based operating systems (such as GNU/Linux, and FreeBSD) and IBM OS/2, Novell NetWare, macOS and Windows. Moreover, other anti-virus products have been developed to deliver protection for devices that run Android, Symbian, BlackBerry, and Windows Mobile.

Components of Dr.Web Industrial for UNIX File Servers are constantly updated, and virus databases are regularly supplemented with new signatures to ensure up-to-date protection of servers, workstations and user programs and data. To provide additional protection against unknown viruses heuristic analysis methods are implemented in the scan engine.

## Dr.Web Industrial for UNIX File Servers Main Functions

1. **Detection and neutralization of threats.** Searches for malicious programs (for example, viruses, including those that infect mail files and boot records, trojans, mail worms) and unwanted software (for example, adware, joke programs, dialers, and so on). To find more information on computer threat types, refer to [Appendix A. Types of Computer Threats](#).

Threat detection methods:



- *signature analysis*, which allows detection of known threats;
- *heuristic analysis*, which allows detection of threats that are not present in virus databases.



The heuristic analyzer may raise false positive detections. Thus, objects that contain threats detected by the analyzer are considered “suspicious”. It is recommended that you choose to quarantine such files and send them for analysis to Doctor Web anti-virus laboratory. For details on methods used to neutralize threats, refer to [Appendix B. Neutralizing Computer Threats](#).

When scanning the file system on the user's request, it is possible of either full scan of all the file system objects available to user, or custom scan of the specified objects only (separate directories or files that meet the specified criteria). In addition, it is possible to perform separate checks of boot records of volumes and executable files which support currently active processes in the system. In the latter case, when a threat is detected, it is not only neutralized the malicious executable file, but all processes running from it are forcibly terminated. In systems that implement a mandatory model of access to files with a set of different access levels, the scanning of files that are not available at the current access level can be done in special [autonomous copy](#) mode.

All objects containing threats detected in the file system are registered in the permanently stored threats registry, except those threats that were detected in the autonomous copy mode.

The [Dr.Web Ctl](#) command-line tool included in Dr.Web Industrial for UNIX File Servers, allows to scan for threats file systems of remote network hosts, that provide remote terminal access via SSH or Telnet.



The remote scanning can be used only for detection of malicious and suspicious files on a remote host. To eliminate detected threats on the remote host, it is necessary to use administration tools provided directly by this host. For example, for routers and other “smart” devices, a mechanism for a firmware update can be used; for computing machines, it can be done via a connection to them (as an option, using a remote terminal mode) and respective operations in their file system (removal or moving of files, and so on), or via running an anti-virus software installed on them.

## 2. Monitoring access to files:

- **file system in the OS.** Monitors file events and attempts to run executables. This feature allows to detect and neutralize malware at an attempt to infect the server file system. Besides the standard monitoring mode, you can enable the enhanced (Paranoid) mode in which the monitor blocks access to files until their scanning is finished (it allows you to prevent access to an infected file but the scanning result is available after an app gets access to the file). The enhanced mode increases the security level but slows down the access to the file that are not scanned yet.



Volume monitoring function is available only for operating systems of GNU/Linux family. For other [supported](#) operating systems the component which provides this feature is not in the package.



- **Samba shared directories.** Read and write operations of local and remote users of the file server are monitored. This feature allows to detect and neutralize malware at an attempt to save a malicious program to the file storage, which prevents its distribution over the network.



Note that the Novell Storage Services volume monitoring function is available only for Novell Open Enterprise Server SP2 SUSE Linux Enterprise Server operating system 10 SP3 or later. For other [supported](#) operating systems the component which provides this feature is not in the package.

3. **Reliable isolation of infected or suspicious objects.** Such objects detected in the server's file system are moved to a special storage, quarantine, to prevent any harm to the system. When moved to quarantine, objects are renamed according to special rules and, if necessary, they can be restored to their original location only on demand.
4. **Automatic update** of the scan engine, virus databases for the maintenance of the high level of protection against malware.
5. **Collection of statistics** on virus events; logging threat detection events. Sending of notifications on detected threats over SNMP to external monitoring systems and to the centralized protection server if Dr.Web Industrial for UNIX File Servers operates in the [centralized protection mode](#).
6. **Operation in the centralized protection mode** (when connected to the centralized protection server, such as Dr.Web Enterprise Server or as a part of Dr.Web AV-Desk service). This mode allows implementation of a [unified security policy](#) on computers within the protected network. It can be a corporate network, a private network (VPN), or a network of a service provider (for example, an internet service provider).

## Structure of Dr.Web Industrial for UNIX File Servers

Dr.Web Industrial for UNIX File Servers is a product consisting of a set of components, where each component has its own set of functions. The components are separated into the following categories according to their objectives:

- [basic anti-virus components](#) which form Dr.Web Industrial for UNIX File Servers core. In the absence of the components under this category, the product cannot scan files (and other data) for viruses and other threats;
- [threat search components](#). These components are used to solve Dr.Web Industrial for UNIX File Servers basic tasks—detecting threats and potentially dangerous objects. In their operation the components falling under this category use basic anti-virus components;
- [service components](#), which solve the auxiliary anti-virus protection issues (anti-virus databases updates, centralized protection servers connection, common Dr.Web Industrial for UNIX File Servers operation managing, and so on);
- [interface components](#), which provide (the user or third party applications) with the interface for Dr.Web Industrial for UNIX File Servers.

Below is the list of Dr.Web Industrial for UNIX File Servers components.



## 1. Basic Anti-virus Components

Component	Description
Dr.Web Virus-Finding Engine	<p>An anti-virus engine. Implements <a href="#">algorithms</a> to detect <a href="#">viruses and malicious programs</a> (by using a signature and heuristic analysis).</p> <p>Managed by Dr.Web Scanning Engine</p> <hr/> <p>Library file: <code>drweb32.dll</code>.</p> <p>Internal name displayed in the log file: <code>CoreEngine</code></p>
<a href="#">Dr.Web Scanning Engine</a>	<p>A scan engine. This component loads Dr.Web Virus-Finding Engine and anti-virus databases.</p> <ul style="list-style-type: none"><li>• Sends the contents of files and boot records to the anti-virus engine for scanning.</li><li>• Manages a queue of the files to be scanned.</li><li>• Cures threats to which this action is applicable.</li></ul> <p>Is operated by Dr.Web ConfigD or can operate autonomously.</p> <p>Used by Dr.Web File Checker and Dr.Web Network Checker components. Also can be used by Dr.Web MeshD components (in some operation modes) and by external (in relation to Dr.Web Industrial for UNIX File Servers) applications specifically using Dr.Web Scanning Engine API</p> <hr/> <p>Executable file: <code>drweb-se</code>.</p> <p>Internal name displayed in the log: <code>ScanEngine</code></p>
Virus databases	<p>An automatically updated database of signatures of viruses and other threats, as well as of malicious software detection and neutralization algorithms.</p> <p>Used by Dr.Web Virus-Finding Engine and bundled with it</p>
<a href="#">Dr.Web File Checker</a>	<p>A component for scanning file system objects and a quarantine manager.</p> <ul style="list-style-type: none"><li>• Receives tasks from the threat scanning component on scanning files in the local (in relation to Dr.Web Scanning Engine) file system.</li><li>• Surfs the file system directories according to the task, sends files for scanning to Dr.Web Scanning Engine and notifies client components about the scanning progress.</li><li>• Deletes infected files, moves them to and restores them from quarantine, manages <a href="#">quarantine directories</a>.</li><li>• Builds the cache and keeps it up-to-date. The cache contains information about previously scanned files to reduce the periodicity of rescanning files.</li></ul> <p>Used by components that scan file system objects, such as SpIDer Guard, SpIDer Guard for SMB</p> <hr/>




Component	Description
	Executable file: <code>drweb-filecheck</code> . Internal name displayed in the log: <code>FileCheck</code>
<a href="#">Dr.Web Network Checker</a>	<p>A network data scanning agent.</p> <ul style="list-style-type: none"><li>• Used to send data to the scan engine. The data is sent by components of the product over the network.</li><li>• Allows Dr.Web Industrial for UNIX File Servers to manage distributed file scanning: to receive/transmit files for scanning from/to remote hosts. For that purpose, the remote hosts must feature an installed and running Dr.Web for UNIX operating systems. In the distributed scanning mode, it allows automatic distribution of scanning load among remote hosts by reducing load on hosts with a large number of scanning tasks (for example, on mail servers, file servers, internet gateways).</li></ul> <p>If partner hosts that can receive data for scanning are present on the network, the components that use Dr.Web Network Checker for scanning may not use local Dr.Web Scanning Engine. Thus, Dr.Web Scanning Engine, Dr.Web Virus-Finding Engine and anti-virus databases may be absent.</p> <p>For security reasons, files are transmitted over the network using SSL</p> <p>Executable file: <code>drweb-netcheck</code>. Internal name displayed in the log: <code>NetCheck</code></p>
<a href="#">Dr.Web MeshD</a>	<p>A component that connects Dr.Web Industrial for UNIX File Servers to the local cloud, which allows Dr.Web for UNIX products to exchange updates, results of file scanning, transmit files to each other for scanning, as well as provide scan engine services directly.</p> <p>If the product includes this component, a local cloud to which this component is connected, as well as hosts providing scan engine services, Dr.Web Scanning Engine, Dr.Web Virus-Finding Engine and anti-virus databases may be absent</p> <p>Executable file: <code>drweb-meshd</code>. Internal name displayed in the log: <code>MeshD</code></p>

## 2. Threat Search Components

Component	Description
<a href="#">SplDer Guard</a>	<p>Linux file system monitor.</p> <p>A resident mode component that tracks file operations (such as creating, opening, closing, and launching) in GNU/Linux file systems. It sends requests to Dr.Web File Checker to scan the contents of new and modified files, as well as executable files when opening programs.</p>



Component	Description
	<p>Depending on OS features, uses the <i>fanotify</i> mechanism (API provided by the OS). When the <i>fanotify</i> system mechanism is used, the monitor can operate in an enhanced mode, blocking access to not yet checked files (all types or executables only) until the scan is completed. By default, the enhanced monitoring mode is <a href="#">disabled</a>.</p> <div> It is included only in the distributions designed for GNU/Linux OSes.</div> <p>Executable file: <code>drweb-spider</code>. Internal name displayed in the log: <code>LinuxSpider</code></p>
<a href="#">SpIDer Guard for SMB</a>	<p>Samba shared directories monitor.</p> <p>Operates in a background mode and monitors file system operations (such as creating, opening, closing, as well as reading and writing) in directories selected as the Samba server file storages. Sends requests to Dr.Web File Checker for scanning the contents of new or modified files.</p> <p>For integration with the file server uses VFS SMB modules that operate on Samba server side</p> <p>Executable file: <code>drweb-smbspider-daemon</code>. Internal name displayed in the log: <code>SMBSpider</code></p>

### 3. Service Components

Component	Description
<a href="#">Dr.Web ConfigD</a>	<p>Dr.Web Industrial for UNIX File Servers configuration daemon.</p> <ul style="list-style-type: none"><li>Starts and stops other product components depending on the settings.</li><li>Restarts components if a failure in their operation occurs. Starts components at the request of other components. Informs active components when another component starts or shuts down.</li><li>Stores information about present license keys and settings and provides this information to all components. Receives adjusted settings and license keys from the components of Dr.Web Industrial for UNIX File Servers expected to provide such information. Notifies other components on changes in license keys and settings</li></ul> <p>Executable file: <code>drweb-configd</code>. Internal name displayed in the log file: <code>ConfigD</code></p>
<a href="#">Dr.Web ES Agent</a>	<p>The centralized protection agent. Ensures product operation in the centralized protection and mobile <a href="#">modes</a>.</p>



Component	Description
	<ul style="list-style-type: none"><li>Provides connection between the product and the centralized protection server, receives a <a href="#">license</a> key file, updates of the virus databases and anti-virus engine.</li><li>Sends to the server information on the components included in Dr.Web Industrial for UNIX File Servers and their status as well as statistics of virus events</li></ul> <hr/> <p>Executable file: <code>drweb-esagent</code>.</p> <p>Internal name displayed in the log: <code>ESAgent</code></p>
<a href="#">Dr.Web StatD</a>	<p>A component for storing Dr.Web Industrial for UNIX File Servers component operation events.</p> <p>Receives and stores events of the product components (such as abnormal termination, threat detection, and so on)</p> <hr/> <p>Executable file: <code>drweb-statd</code>.</p> <p>Internal name displayed in the log file: <code>StatD</code></p>
<a href="#">Dr.Web Updater</a>	<p>An updating component.</p> <p>Downloads from Doctor Web servers updates of the virus databases, the anti-virus engine.</p> <p>The updates can be downloaded automatically, according to the schedule, and on user demand (via Dr.Web Ctl or management web interface)</p> <hr/> <p>Executable file: <code>drweb-update</code>.</p> <p>Internal name displayed in the log: <code>Update</code></p>

#### 4. Interface Components

Component	Description
<a href="#">Dr.Web HTTPD</a>	<p>Dr.Web Industrial for UNIX File Servers management web server.</p> <p>Provides a custom HTTP API for managing Dr.Web Industrial for UNIX File Servers components.</p> <p>The specified API is used by the management web interface (must be installed separately).</p> <p>For security reasons, the component uses HTTPS to connect to the web interface.</p> <p>Uses Dr.Web Network Checker to transmit data for scanning to Dr.Web Scanning Engine</p> <hr/> <p>Executable file: <code>drweb-httpd</code>.</p> <p>Internal name displayed in the log: <code>HTTPD</code></p>






Component	Description
<a href="#">Dr.Web Web Management Interface</a>	<p>Management Web Interface.</p> <p>The interface can be accessed using any browser on a local or remote host. The web interface enables the product not to use third-party web servers (such as Apache HTTP Server) or remote administration tools, such as Webmin.</p> <p>The component functionality is provided by Dr.Web HTTPD component</p>
<a href="#">Dr.Web Ctl</a>	<p>A tool for managing Dr.Web Industrial for UNIX File Servers from the command line.</p> <p>Allows the user to start file scanning, view and manage quarantined objects, start a virus database update procedure, connect Dr.Web Industrial for UNIX File Servers to or disconnect it from the centralized protection server, view and configure product parameters</p> <hr/> <p>Executable file: <code>drweb-ctl</code>.</p> <p>Internal name displayed in the log: <code>Ctl</code></p>
<a href="#">Dr.Web SNMPD</a>	<p>An SNMP agent.</p> <p>Designed for integration of Dr.Web Industrial for UNIX File Servers with external monitoring systems over SNMP. Such integration allows you to monitor the state of the product components and to collect statistics on threat detection and neutralization.</p> <p>Supports SNMP v2c and v3</p> <hr/> <p>Executable file: <code>drweb-snmpd</code>.</p> <p>Internal name displayed in the log: <code>SNMPD</code></p>



The figure below shows the structure of Dr.Web Industrial for UNIX File Servers and its operation with external applications.



**Figure 1. The structure of Dr.Web Industrial for UNIX File Servers**

In this scheme, the following notations are used:

	—Dr.Web Industrial for UNIX File Servers as a whole and external Dr.Web applications not included in the solution
	—programs external to Dr.Web Industrial for UNIX File Servers and products that integrate with it
	—the service components that perform particular anti-virus protection tasks (anti-virus databases updates, centralized protection servers connection, overall coordination of operations, and so on)
	—components that provide (the user or third party applications) with the interface to manage Dr.Web Industrial for UNIX File Servers
	—components used for anti-virus scanning
	—basic anti-virus components that form the Dr.Web Industrial for UNIX File Servers core. Used by the components that perform data and files scans

Components marked with a dashed line can be missing depending on the Dr.Web Industrial for UNIX File Servers distribution and usage.

For details on Dr.Web Industrial for UNIX File Servers components, refer to [Dr.Web Industrial for UNIX File Servers Components](#).



## Placing in Quarantine

Quarantine directories of Dr.Web Industrial for UNIX File Servers serve for isolation of files that pose a threat to system security and cannot be currently cured. Such threats are those that are unknown to Dr.Web Industrial for UNIX File Servers (that is, a virus is detected by the heuristic analyzer but the virus signature and method to cure are absent in the databases) or those that caused an error during curing. Moreover, a file can be quarantined at user request if the user selected this [action](#) in the list of detected threats or specified this action in settings as reaction to this threat [type](#).

When a file is quarantined, it is renamed according to special rules. Renaming of isolated files prevents their identification by users or applications and complicates access to them in case of attempt to bypass quarantine management tools implemented in Dr.Web Industrial for UNIX File Servers. Moreover, when a file is moved to quarantine, the execution bit is reset to prevent an attempt to run this file.

Quarantine directories are located in:

- *user home directory* (if multiple user accounts exist on the computer, a separate quarantine directory can be created for each of the users);
- *root directory of each logical volume* mounted to the file system.

Dr.Web quarantine directories are always named as `.com.drweb.quarantine` and are not created until the **Quarantine** [action](#) is applied. At that, only a directory required for isolation of a concrete object is created. When selecting a directory, the file owner name is used: search is performed upwards from the location where the malicious object resides and if the owner home directory is reached, the quarantine storage created in this directory is selected.

Otherwise, the file is isolated in the quarantine created in the root directory of the volume (which is not always the same as the file system root directory). Thus, any infected file moved to quarantine is always located on the volume, which provides for correct operation of quarantine in case several removable data storages and other volumes are mounted to different locations in the system.

A user can manage quarantine contents from the command line using the utility [Dr.Web Ctl](#), or via the [management web interface](#) (if it is installed). Every action is applied to the consolidated quarantine; that is, changes affect all quarantine directories available at the moment.





Operation with quarantined objects is allowed even if no [active license](#) is found. However, isolated objects cannot be cured in this case.



## File Permissions and Privileges

To scan objects of the file system and neutralize threats, Dr.Web Industrial for UNIX File Servers (or rather the user under whom it runs) requires the following permissions:

Action	Required rights
Listing all detected threats	Unrestricted. No special permission required
List archive contents (display only corrupted or malicious elements)	Unrestricted. No special permission required
Moving to quarantine	Unrestricted. The user can quarantine all infected files regardless of read or write permissions on them
Deleting threats	<p>The user needs to have write permissions for the file that is being deleted.</p> <div> If threat is detected in a file located in a container (an archive, email message, and so on), its removal is replaced with moving of a container to quarantine.</div>
Curing	<p>Unrestricted. The access permissions and owner of a cured file remain the same after curing.</p> <div> The file can be removed if deletion can cure the detected threat.</div>
Restoring a file from quarantine	The user should have permissions to read the file and to write to the restore directory
Deleting a file from quarantine	The user must possess write permissions to the file that was moved to quarantine

To enable operation of the command-line management [Dr.Web Ctl](#) tool with superuser (*root*) privileges, you can use the `su` command, which allows to change the user, or the `sudo` command, which allows you to execute a command as another user.



The Dr.Web Scanning Engine scan engine cannot scan file which size exceeds 4 GB (on attempt to scan such files, the following error message displays: *"File is too large"*).



## Operation Modes


Dr.Web Industrial for UNIX File Servers can operate both in standalone mode and as a part of an *anti-virus network* managed by a *centralized protection server*. Operation in the *centralized protection mode* does not require installation of additional software or Dr.Web Industrial for UNIX File Servers re-installation or removal.

- *In Standalone mode*, the protected computer is not connected to an anti-virus network and its operation is managed locally. In this mode, configuration and license key files are located on local disks and Dr.Web Industrial for UNIX File Servers is fully controlled from the protected computer. Updates to virus databases are received from Doctor Web update servers.
- *In the centralized protection mode (enterprise mode)*, protection of the computer is managed by the centralized protection server. In this mode, some functions and settings of Dr.Web Industrial for UNIX File Servers can be adjusted in accordance with the general (corporate) anti-virus protection policy implemented on the anti-virus network. The license key file used for operating in the centralized protection mode is received from the centralized protection server. The demo key file stored on the local computer, if any, is not used. Statistics on virus events together with information on Dr.Web Industrial for UNIX File Servers operation are sent to the centralized protection server. Updates to virus databases are also received from the centralized protection server.
- *In the mobile mode*, Dr.Web Industrial for UNIX File Servers receives updates from Doctor Web update servers, but operation of the product is managed with the local settings and a license key file received from the centralized protection server. You can switch to the mobile mode only if it is allowed in the centralized protection server settings.

## Centralized Protection Concept

Doctor Web solutions for centralized protection use client-server model (see the figure below).

Workstations and servers are protected from threats by *local anti-virus components* (herein, Dr.Web Industrial for UNIX File Servers components) installed on them, which provides for anti-virus protection of remote computers and allows connection between the workstations and the centralized protection server.



**Figure 2. Logical structure of the Anti-virus Network**

Local computers are updated and configured from the *centralized protection server*. The stream of instructions, data and statistics in the anti-virus network goes also through the centralized protection server. The volume of traffic between protected computers and the central server can be quite sizeable, therefore solutions provide options for traffic compression. To prevent leak of sensitive data or substitution of software downloaded onto protected computers, encryption is also supported.

All necessary updates are downloaded to the centralized protection server from Doctor Web update servers.

Local anti-virus components are configured and managed from the centralized protection server according to commands received from anti-virus network administrators. Administrators manage centralized protection servers and topology of anti-virus networks (for example,



validate connections to the centralized protection server from remote computers) and configure operation of local anti-virus components when necessary.



Local anti-virus components are not compatible with anti-virus products of other companies or anti-virus solutions of Doctor Web if the latter do not support operation in the centralized protection mode (for example, Dr.Web Anti-virus, version 5.0). Installation of two anti-virus programs on the same computer can cause a system crash and loss of important data.

Centralized protection mode allows exporting and saving operation reports using the centralized protection center. Reports can be exported and saved in the following formats: HTML, CSV, PDF, and XML.

## Connection to the centralized protection server

Dr.Web Industrial for UNIX File Servers can be connected to the centralized protection server of an anti-virus network using the `esconnect` [command](#) of the [Dr.Web Ctl](#) command-line-based management tool.



For the verification of the centralized protection server the certificate corresponding to the unique public key of the server is used. By default, the Dr.Web ES Agent centralized protection agent will not allow you to connect to the server unless you specify the certificate file. The certificate file must first be obtained from the administrator of the anti-virus network served by the server to which you want to connect Dr.Web Industrial for UNIX File Servers.

If Dr.Web Industrial for UNIX File Servers is connected to the centralized protection server, you can switch the product into the mobile mode or switch it back into the centralized protection mode. Switching the mobile mode on or off is accomplished with the help of the `MobileMode` [configuration parameter](#) of the [Dr.Web ES Agent](#) component.



Dr.Web Industrial for UNIX File Servers can switch to the mobile mode only if it is allowed in the settings on the centralized protection server.

## Disconnecting from an Anti-Virus Network

Dr.Web Industrial for UNIX File Servers can be disconnected from the centralized protection server of an anti-virus network using the `esdisconnect` [command](#) of the [Dr.Web Ctl](#) command-line-based management tool.



## System Requirements and Compatibility

### In this section

- [System Requirements](#)
- [List of Supported Operating System Versions](#)
- [Additional Packages and Components](#)
- [Disclaimer](#)
- [Supported File Servers](#)
- [Compatibility with Security Subsystems](#)

### System Requirements

You can use Dr.Web Industrial for UNIX File Servers on a computer that meets the following requirements:

Component	Requirement
Platform	Processors of the following architectures and command systems are supported: <ul style="list-style-type: none"><li>• Intel/AMD: 32-bit (<i>IA-32, x86</i>); 64-bit (<i>x86-64, x64, amd64</i>)</li><li>• ARM64</li><li>• E2K (<i>Elbrus</i>)</li><li>• IBM POWER9, Power10 (<i>ppc64el</i>)</li></ul>
RAM	At least 500 MB of free RAM (1 GB or more is recommended)
Free disk space	At least 2 GB of free disk space on a volume where the product directories are located
Operating system	GNU/Linux (based on kernel version 2.6.37 or later, using <code>glibc</code> library 2.13 or later, <code>systemd</code> initialization system ver. 209 or later), FreeBSD. The supported operating system versions are listed below.  The operating system must support the PAM authentication mechanism
Other	The following valid network connections: <ul style="list-style-type: none"><li>• valid Internet connection to enable updates for virus databases and Dr.Web components;</li><li>• when operating in the centralized protection mode, connection to the server on the local network is enough; connection to the Internet is not required</li></ul>





To ensure the correct operation Dr.Web Industrial for UNIX File Servers, open the following ports:

Purpose	Direction	Port numbers
To receive updates	outgoing	80

## List of Supported Operating System Versions

### • GNU/Linux

Platform	Supported GNU/Linux versions
x86_64	<ul style="list-style-type: none"><li>• ALT 8 SP</li><li>• ALT Server 9, 10</li><li>• ALT Workstation 9, 10</li><li>• Astra Linux Common Edition (Orel) 2.12</li><li>• Astra Linux Special Edition 1.5 (with cumulative patch 20201201SE15), 1.6 (with cumulative patch 20200722SE16), 1.7</li><li>• CentOS 7, 8</li><li>• Debian 9, 10, 11, 12</li><li>• Fedora 37, 38</li><li>• GosLinux IC6</li><li>• Red Hat Enterprise Linux 7, 8</li><li>• RED OS 7.2 MUROM, RED OS 7.3 MUROM</li><li>• SUSE Linux Enterprise Server 12 SP3</li><li>• Ubuntu 18.04, 20.04, 22.04</li></ul>
x86	<ul style="list-style-type: none"><li>• ALT 8 SP</li><li>• ALT Workstation 9, 10</li><li>• CentOS 7</li><li>• Debian 10</li></ul>
ARM64	<ul style="list-style-type: none"><li>• ALT 8 SP</li><li>• ALT Server 9, 10</li><li>• ALT Workstation 9, 10</li><li>• Astra Linux Special Edition (Novorossiysk) 4.7</li><li>• CentOS 7, 8</li><li>• Debian 11, 12</li><li>• Ubuntu 18.04</li></ul>
E2K	<ul style="list-style-type: none"><li>• ALT 8 SP</li><li>• Astra Linux Special Edition (Leningrad) 8.1 (with cumulative patch 8.120200429SE81)</li><li>• Elbrus-D MCST 1.4</li></ul>



Platform	Supported GNU/Linux versions
	<ul style="list-style-type: none"><li>• GS CS Elbrus 8.32 TVGL.00311-28</li></ul>
ppc64el	<ul style="list-style-type: none"><li>• CentOS 8</li><li>• Ubuntu 20.04</li></ul>



In ALT 8 SP, Elbrus-D MCST 1.4 and GosLinux IC6 mandatory access control is not supported.

For other GNU/Linux versions that meet the abovementioned requirements full compatibility with Dr.Web Industrial for UNIX File Servers is not guaranteed. If a compatibility issue occurs, contact [technical support](#).

- **FreeBSD**

Platform	Supported FreeBSD versions
x86	11, 12, 13
x86_64	11, 12, 13



For FreeBSD OS, Dr.Web Industrial for UNIX File Servers can be installed only from the [universal package](#).

## Additional Packages and Components

Dr.Web Industrial for UNIX File Servers does not require installation of additional packages and OS components (except for the protected server software, see below).



For convenient work with Dr.Web Industrial for UNIX File Servers in the [command line](#), you can enable command auto-completion in your command shell (if disabled).

---

If you encounter any problem with installation of additional packages and components, refer to the documentation of your operating system version.

## Disclaimer

- SplDer Guard can operate in the enhanced (Paranoid) [mode](#), which blocks access to the files that have not been scanned yet, *only* via fanotify and providing that an OS kernel is built with the enabled `CONFIG_FANOTIFY_ACCESS_PERMISSIONS` option.



## Supported File Servers

### Samba File Service

For [integration](#) with Samba file service, the installed and configured file server Samba is required (supported Samba versions 3.6–4.16).



The SpliDer Guard for SMB monitor of Dr.Web Industrial for UNIX File Servers uses a special VFS SMB module for the integration with the Samba server. With the SpliDer Guard for SMB component, several versions of this module are supplied. They are built for various versions of Samba. However, the supplied versions of the VFS SMB module may be incompatible with the version of Samba installed on your file server. It may occur, for example, if your Samba server uses the `CLUSTER_SUPPORT` option.

If VFS SMB modules are incompatible with your Samba server, the *corresponding message* is shown during the Dr.Web Industrial for UNIX File Servers [installation](#). In this case, build the VFS SMB module for your Samba server manually (including the compatibility with the `CLUSTER_SUPPORT` option if necessary).

The procedure of building the VFS SMB module from the supplied source code files is described in the [Building the VFS SMB Module](#) section.

## Compatibility with Security Subsystems

By default, Dr.Web Industrial for UNIX File Servers does not support SELinux. In addition, Dr.Web Industrial for UNIX File Servers operates in reduced functionality mode in the GNU/Linux systems that use mandatory access models (for example, in systems supplied with the PARSEC mandatory access subsystem that appends different privilege levels to users and files).

If installation of Dr.Web Industrial for UNIX File Servers is required for systems with SELinux (as well as for systems that use mandatory access models). It is necessary to execute additional settings of a security subsystem so that Dr.Web Industrial for UNIX File Servers operates in full functionality mode. For details, refer to the section [Configuring Security Subsystems](#).



## Licensing

Permissions to use Dr.Web Industrial for UNIX File Servers are granted by the *license* purchased from the Doctor Web company or from its partners. License parameters determining user rights are set in accordance with the License agreement (see <https://license.drweb.com/agreement/>), which the user accepts during Dr.Web Industrial for UNIX File Servers installation. The license contains information on the user and the vendor as well as usage parameters of the purchased copy, including:

- list of components licensed to the user;
- Dr.Web Industrial for UNIX File Servers license period;
- other restrictions (for example, number of computers on which the purchased copy is allowed for use).

For evaluation purposes users can also activate the *demo period*. After successful activation, demo period provides users with full functionality of Dr.Web Industrial for UNIX File Servers for the whole activated period.

Each Doctor Web product license has a unique serial number associated with a special file stored on the user computer. This file regulates operation of components in accordance with the license parameters and is called a *license* key file. Upon activation of a demo period, a special key file, named a *demo* key file, is automatically generated.

If a license or a demo period are not activated on the computer, Dr.Web Industrial for UNIX File Servers components are blocked. Moreover, updates for virus databases and components cannot be downloaded from Doctor Web update servers. But you can activate Dr.Web Industrial for UNIX File Servers by connecting it to the centralized protection server as a part of the [anti-virus network](#) administered by the enterprise or internet service provider. In this case, operation of anti-virus and updating are managed by the centralized protection server.



## Installing and Uninstalling

### In this section

- [Installing Dr.Web Industrial for UNIX File Servers](#)
- [Upgrading Dr.Web Industrial for UNIX File Servers](#)
- [Uninstalling Dr.Web Industrial for UNIX File Servers](#)
- [Configuring Security Subsystems](#)
- Additional information:
  - [Dr.Web Industrial for UNIX File Servers Packages and Files](#)
  - [Custom Component Installation and Uninstallation](#)

This section describes how to install and uninstall Dr.Web Industrial for UNIX File Servers. In this section, you can also find information on how to obtain current updates and a procedure of upgrading to a new version, if the previous version of Dr.Web Industrial for UNIX File Servers is already installed on your computer.

Besides, this section describes the procedure of custom installation and uninstallation of Dr.Web Industrial for UNIX File Servers components (for example, to resolve errors that occurred during the course of the Dr.Web Industrial for UNIX File Servers operation or to get an installation with a limited function set) and configuration of advanced security subsystems (such as SELinux) that could be necessary for installation and operation of Dr.Web Industrial for UNIX File Servers.

To perform these procedures, superuser permissions are required (i.e. privileges of the *root* user). To elevate your privileges, use the `su` command for changing the current user or the `sudo` command to execute the specified command with the privileges of another user.



Compatibility is not guaranteed for Dr.Web Industrial for UNIX File Servers and anti-virus products of other developers. Due to the fact that installation of two anti-viruses on one machine can lead to errors in the operation system and loss of important data, before the installation of Dr.Web Industrial for UNIX File Servers, it is strongly recommended that you delete anti-virus products of other developers from the computer.

If your computer already has other Dr.Web anti-virus product installed from the [universal package](#) (.run), and you want to install one more Dr.Web anti-virus product (for example, you have Dr.Web for Linux from the universal package installed, and in addition you want to install Dr.Web Industrial for UNIX File Servers), it is necessary to make sure that the version of the installed product is the same as the version of Dr.Web Industrial for UNIX File Servers you want to install. If the product version that you plan on installing is newer than the installed product version, before installation, it is necessary to [upgrade](#) the installed Dr.Web Industrial for UNIX File Servers to the version of the product you want to install additionally.

For FreeBSD OS, Dr.Web Industrial for UNIX File Servers can be installed only from the [universal package](#).

## Installing Dr.Web Industrial for UNIX File Servers

To install Dr.Web Industrial for UNIX File Servers, do one of the following:

1. From the Doctor Web official website, download the installation file that contains a [universal package](#) for UNIX systems. The package includes an installer (due to the fact that the installation program is developed for the command-line mode, for its operation in the graphical desktop mode, you will need to have a terminal emulator available).
2. Download the [native packages](#) from the corresponding package repository of Doctor Web.



For FreeBSD OS, Dr.Web Industrial for UNIX File Servers can be installed only from the [universal package](#).



In OSs using the outdated versions of the package manager (for instance, ALT 8 SP) it is recommended to install the Dr.Web Industrial for UNIX File Servers [universal package](#).

During the installation (as well as from universal .run package, as from native packages using package manager), on root@localhost email address messages containing installation results are sent.

After you installed Dr.Web Industrial for UNIX File Servers by any of the mentioned means, you can [uninstall](#) or [update](#) it if there are fixes for its components available or if a new Dr.Web Industrial for UNIX File Servers version is released. If required, you can also [configure security subsystems](#) of GNU/Linux for correct operation of Dr.Web Industrial for UNIX File Servers. If there is a problem with functioning of any individual components, you can perform their



[custom installation and uninstallation](#), without uninstalling Dr.Web Industrial for UNIX File Servers.

Regardless of the selected way to install Dr.Web Industrial for UNIX File Servers, after the installation completes, you need to activate the license and to install the received key file. Moreover, you can [connect](#) Dr.Web Industrial for UNIX File Servers to the centralized protection server. For details, refer to [Licensing](#). Unless you do it, anti-virus protection functions will be switched off. In addition, in some cases it is necessary to customize the basic functionality of the installed Dr.Web Industrial for UNIX File Servers, as described in the [Getting Started](#) section.

## Installing the Universal Package

Dr.Web Industrial for UNIX File Servers universal package is distributed as an installation file named `drweb-<version>-av-srv-<OS>-<platform>.run`, where `<OS>` is a type of UNIX-like OS, `<Platform>` is the platform for which Dr.Web Industrial for UNIX File Servers is intended (for 32-bit platforms—`x86`, for 64-bit platforms—`amd64`, `arm64` and `e2s`). For example:

```
drweb-11.1.0-av-srv-linux-x86.run
```



The installation file name corresponding to the above-mentioned format is referred to as `<file_name>.run` below in this section.

### To install Dr.Web Industrial for UNIX File Servers components

1. If you do not have the installation file containing the universal package, download it from the Doctor Web official website: <https://download.drweb.com/>.
2. Save the installation file to the hard disk drive of your computer.
3. Allow the archive to be executed, for example, by using the command:

```
# chmod +x <file_name>.run
```

4. Execute the archive using the command:

```
# ./<file_name>.run
```

or use the standard file manager of the graphical shell for both changing the file properties (permissions) and running the file.



In case of installation on Astra Linux SE version 1.6 operating system that functions in the *closed software environment* mode, a failure of the installation program launch may occur due to Doctor Web public key absence in trusted keys list. In this case, you need to pre-configure the *closed software environment* mode (see [Configuring the Launch in the CSE Mode \(Astra Linux SE 1.6 and 1.7\)](#)), then restart the installation program.



This will run an integrity check of the archive, after which the archived files are unpacked to a temporary directory and an installation program is started. If the user does not have root privileges, the installation program attempts to elevate its privileges asking you for the root password (`sudo` is used). If the attempt fails, the installation process aborts.



If the path to the temporary directory in the file system has not enough free space for the unpacked files, the installation process is aborted and an appropriate message is displayed. In this case, change the value of the `TMPDIR` system environment variable so that it points to a directory with enough free space and repeat the installation. You can also use the `--target` option.

After that the installer for the [command-line mode](#) is automatically started (to run it in a graphical desktop environment, you need any terminal emulator).

5. Follow the installer instructions.
6. You can also start the installation program in a silent mode by executing the command:

```
# ./<file_name>.run -- --non-interactive
```

In this case the installation program is started in the silent mode and will operate without a user interface (this means it also will not have any dialogs that are normally displayed in the command-line mode).



Using this option means that you accept the terms of the Dr.Web License Agreement. The License Agreement text is located in the `/opt/drweb.com/share/doc/LICENSE` file. The file extension indicates the language of the License Agreement. If the `LICENSE` file does not have any extension, the Dr.Web License Agreement is written in English. If you do not accept the terms of the License Agreement, [uninstall](#) Dr.Web Industrial for UNIX File Servers after its installation.

---

Administrative (root) privileges are required to start the uninstall program in silent mode. To elevate the privileges, you can use the `su` and `sudo` commands.



If your GNU/Linux distribution features SELinux, the installation process can be interrupted by the security subsystem. If such a situation occurs, set SELinux to the *Permissive* mode with the command:

```
# setenforce 0
```

And restart the installer. After the installation completes, configure SELinux [security policies](#) to enable correct operation of the product components.

---

For details on conventions for `<opt_dir>`, `<etc_dir>`, and `<var_dir>`, refer to the [Introduction](#).

All unpacked installation files are deleted once the installation process completes.





It is recommended that you save the `<file_name>.run` file, from which the installation was performed, to reinstall Dr.Web Industrial for UNIX File Servers or its components without the need to update its version.

## Installing from the Command Line

Once you start the program for the command-line-based installation, a message will be displayed inviting you to install the product.

1. To start installation, enter `Yes` or `Y` in response to the "Do you want to continue?" question. To exit the installer, enter `No` or `N`. In this case, installation is canceled.
2. After that, you need to view the terms of Dr.Web License Agreement which is displayed on the screen. Press `ENTER` to scroll the text down line by line or `SPACEBAR` to scroll it down one screenful at a time.



Options to scroll the License agreement up are not provided.

3. After you read the License agreement text, you are prompted to accept the terms. Type `Yes` or `Y` if you accept the License agreement. If you refuse to accept it, type `No` or `N`. In the latter case, the installer exits.
4. Once you accept the terms of the License Agreement, installation starts automatically. During the procedure, information about the installation process, including the list of installed Dr.Web components, will be displayed on the screen.
5. If installation completes successfully, a message is displayed that informs you on how to manage Dr.Web Industrial for UNIX File Servers operation.

If an error occurs, a message describing the error is displayed on the screen and then the installer exits. When the installation process fails due to an error, remove the problems that caused this error and start the installation again.

## Installing from the Repository

Dr.Web Industrial for UNIX File Servers native packages are stored in the Dr.Web official repository at <https://repo.drweb.com/>. Once you have added the Dr.Web repository to the list of those used by your operating system package manager, you can install the product from native packages as you install any other programs from the operating system repositories. Required dependencies are automatically resolved.



All the commands mentioned below—the commands used to add repositories, to import digital signature keys, to install and remove packages—must be performed with superuser (root) privileges. To elevate the privileges, use the `su` command (to change the current user) or the `sudo` command (to execute the specified command with another user's privileges).

For the FreeBSD OS, Dr.Web Industrial for UNIX File Servers can be installed only from the [universal package](#).

See below the procedures for the following OS (package managers):

- [Debian, Mint, Ubuntu \(apt\)](#),
- [ALT Linux, PCLinuxOS \(apt-rpm\)](#),
- [Mageia, OpenMandriva Lx \(urpmi\)](#),
- [Red Hat Enterprise Linux, Fedora, CentOS \(yum, dnf\)](#),
- [SUSE Linux \(zypper\)](#).

## Debian, Mint, Ubuntu (apt)

### To install Dr.Web Industrial for UNIX File Servers from the repository

1. The repository for these operating systems is digitally signed by Doctor Web. To access the repository, import and add to the package manager storage the digital signature key via execution of the command:

```
# apt-key adv --keyserver hkp://keyserver.ubuntu.com:80 --recv-keys  
8C42FC58D8752769
```

2. To add the repository, add the following line to the `/etc/apt/sources.list` file:

```
deb http://repo.drweb.com/drweb/debian 11.1 non-free
```



Besides, you can execute items 1 and 2 by downloading from the repository and installing a special DEB package <https://repo.drweb.com/drweb/drweb-repo11.1.deb>.

3. To install Dr.Web Industrial for UNIX File Servers from the repository, use the commands:

```
# apt-get update  
# apt-get install drweb-industrial-file-servers
```

You can also use alternative package managers (for example, Synaptic or aptitude) to install the product. Moreover, it is recommended to use alternative managers, such as aptitude, to solve a package conflict if it occurs.



## ALT Linux, PCLinuxOS (apt-rpm)

### To install Dr.Web Industrial for UNIX File Servers from the repository

1. To add the repository, add the following line to the `/etc/apt/sources.list` file:

```
rpm http://repo.drweb.com/drweb/altlinux 11.1/<arch> drweb
```

where *<arch>*—representation of the package architecture:

- for the 32-bit version: `i386`;
- for the AMD64 architecture: `x86_64`;
- for the ARM64 architecture: `aarch64`;
- for the E2K architecture: `e2s`.

2. To install Dr.Web Industrial for UNIX File Servers from the repository, use the commands:

```
# apt-get update
# apt-get install drweb-industrial-file-servers
```

You can also use alternative package managers (for example, Synaptic or aptitude) to install the product.

## Mageia, OpenMandriva Lx (urpmi)

### To install Dr.Web Industrial for UNIX File Servers from the repository

1. Connect the repository using the command:

```
# urpmi.addmedia drweb https://repo.drweb.com/drweb/linux/11.1/<arch>/
```

where *<arch>*—representation of the package architecture:

- for the 32-bit version: `i386`;
- for the 64-bit version: `x86_64`.

2. To install Dr.Web Industrial for UNIX File Servers from the repository, use the command:

```
# urpmi drweb-industrial-file-servers
```

You can also use alternative package managers (for example, rpmdrake) to install the product.



## Red Hat Enterprise Linux, Fedora, CentOS (yum, dnf)

### To install Dr.Web Industrial for UNIX File Servers from the repository

1. Add a file `drweb.repo` with the contents described below to the `/etc/yum.repos.d` directory:

```
[drweb]
name=DrWeb-11.1
baseurl=https://repo.drweb.com/drweb/linux/11.1/$basearch/
gpgcheck=1
enabled=1
gpgkey=https://repo.drweb.com/drweb/drweb.key
```



If you plan on logging the indicated above contents to a file using such commands as `echo` with redirecting of an output, a symbol `$` must be escaped: `\$`.

Besides, you can execute item 1 by downloading from the repository and installing a special RPM package <https://repo.drweb.com/drweb/drweb-repo11.1.rpm>.

2. To install Dr.Web Industrial for UNIX File Servers from the repository, use the command:

```
# yum install drweb-industrial-file-servers
```

In the Fedora operating system, starting from version 22, it is recommended that instead of manager `yum` the manager `dnf` is used, for example:

```
# dnf install drweb-industrial-file-servers
```

You can also use alternative package managers (for example, PackageKit or Yumex) to install the product.

## SUSE Linux (zypper)

### To install Dr.Web Industrial for UNIX File Servers from the repository

1. To add the repository, use the command:

```
# zypper ar https://repo.drweb.com/drweb/linux/11.1/\$basearch/ drweb
```

2. To install Dr.Web Industrial for UNIX File Servers from the repository, use the commands:

```
# zypper refresh
# zypper install drweb-industrial-file-servers
```

You can also use alternative package managers (for example, YaST) to install the product.



## Upgrading Dr.Web Industrial for UNIX File Servers

Dr.Web Industrial for UNIX File Servers has two update modes.

1. [Getting updates of packages and components](#) released in the course of operation of the current Dr.Web Industrial for UNIX File Servers version (usually such updates contain error fixing and minor improvements in component functioning).
2. [Upgrading to a new version of Dr.Web Industrial for UNIX File Servers](#). This upgrading option is used if Doctor Web released a new version of Dr.Web Industrial for UNIX File Servers you use, and it has new features.



Dr.Web Industrial for UNIX File Servers provides the ability [to update virus databases and the anti-virus engine](#) even without access to the internet on the protected server.

## Updating Packages and Components

After installation of Dr.Web Industrial for UNIX File Servers using any method described in the [corresponding section](#), the package manager automatically connects to the Dr.Web [package repository](#):

- If installation was performed from the [universal package](#) (file `.run`), and the system uses DEB packages (for example, such operating systems as Debian, Mint, Ubuntu), there is no package manager in an operating system (FreeBSD), for operation with Dr.Web packages, an individual version of package managers `zypper` is used. It is automatically installed during the Dr.Web Industrial for UNIX File Servers installation.

To get and install the updated Dr.Web packages with this manager, go to the `<opt_dir>/bin` directory (for GNU/Linux—`/opt/drweb.com/bin`), and execute the commands:

```
# ./zypper refresh
# ./zypper update
```



In the FreeBSD OS 11.x for amd64 a repository update error may occur upon using the `zypper` manager for updates. In this case, install the `compat10x-amd64` support package and try again.

To install the package, use the command:

```
# pkg install compat10x-amd64
```

- In all other cases use commands for updating of the package manager used in your OS, for example:
  - for Red Hat Enterprise Linux and CentOS, use the command `yum`,
  - for Fedora, use the command `yum` or `dnf`,
  - for SUSE Linux, use the command `zypper`,



- for Mageia, OpenMandriva Lx, use the command `urpmi`,
- for Alt Linux, PCLinuxOS, Debian, Mint, Ubuntu, use the command `apt-get`.

You can also use alternate package managers developed for your operating system. If necessary, refer to the instruction manual for the package manager you use.

If a new version of Dr.Web Industrial for UNIX File Servers is released, packages with its components are put into the section of the Dr.Web repository corresponding to the new version. In this case, an update requires switching of the package manager to a new Dr.Web repository section (refer to [Upgrading to a New Product Version](#)).

## Upgrading to a New Product Version

### In this section

- [Introductory Remarks](#)
- [Installing Universal Package for an Upgrade](#)
- [Upgrading from the Repository](#)
- [Key File Transfer](#)
- [Restoring Connection to the Centralized Protection Server](#)

### Introductory Remarks



Before you upgrade to a new version, make sure that your server meets the [system requirements](#) of the new version, including that the necessary programs must be installed.

Your version of Dr.Web Industrial for UNIX File Servers must be upgraded in the same way that was used to install the product.

- If the current version of Dr.Web Industrial for UNIX File Servers was installed from the repository, an upgrade requires updating program packages from the repository.
- If the current version of Dr.Web Industrial for UNIX File Servers was installed from the universal package, then to upgrade Dr.Web Industrial for UNIX File Servers, you need to install another universal package that contains a newer version of the product.



To identify how the product version was installed, check whether the Dr.Web Industrial for UNIX File Servers executable directory contains the `uninst.sh` uninstallation script. If so, the current version was installed from the universal package; otherwise it was installed from the repository.

---

For FreeBSD OS, Dr.Web Industrial for UNIX File Servers can be installed only from the [universal package](#).



If you cannot update Dr.Web Industrial for UNIX File Servers the way you installed it initially, uninstall your current version of Dr.Web Industrial for UNIX File Servers, and then install a new version using any convenient method. Installation and uninstallation procedures for previous Dr.Web Industrial for UNIX File Servers versions are the same as [installation](#) and [uninstallation](#) described in the current manual for the recent version. For additional information, see User manual for your current version of Dr.Web Industrial for UNIX File Servers.

If the current version of Dr.Web Industrial for UNIX File Servers is operating in the [centralized protection](#) mode, it is recommended that you record the address of the centralized protection server. To determine the address to which Dr.Web Industrial for UNIX File Servers is connected, you can use the command:

```
$ drweb-ctl appinfo
```

In the output of this command find the following line:

```
ESAgent; <PID>; RUNNING 1; Connected <address>, on-line
```

save the `<address>` part (which can look like `tcp://<IP address>:<port>`, for example: `tcp://10.20.30.40:1234`). In addition, it is recommended that you save the server certificate file.

In case there are any problems with finding out the parameters of the connection that you are currently using, refer to the Administrator Manual for the Dr.Web Industrial for UNIX File Servers version that you are currently using and to the administrator of your anti-virus network.

## Installing Universal Package for an Upgrade

Install Dr.Web Industrial for UNIX File Servers from the [universal package](#). If an automatic update is impossible, during the installation of the new version, you will get an offer to remove the components of the older version of Dr.Web Industrial for UNIX File Servers installed on your computer automatically.



If during the update process you need to remove the installed Dr.Web Industrial for UNIX File Servers version, and there are multiple Dr.Web server products are installed together on your server (for example, products for file servers, for mail servers, and for internet gateways), you need to select only the packages listed below for removal, in order to keep other products—that will not be upgraded—fully functional:

- `drweb-file-servers-doc`,
- `drweb-smbspider`.



## Upgrading from the Repository

### To upgrade your current version of Dr.Web Industrial for UNIX File Servers installed from the Doctor Web repository

To upgrade your current version of Dr.Web Industrial for UNIX File Servers that was installed from the Doctor Web repository, do one of the following, depending on the required type of packages:

#### • RPM packages (yum, dnf)

1. Change the repository (from the package repository of your current version to the package repository of the recent version).



You can find the name of the repository that stores the packages of the recent version in the [Installing from the Repository](#) section. For details on how to change repositories, refer to help guides of your operating system distribution.

2. Install the new version using the command:

```
# yum update
```

or, if the manager dnf is used (similar to the Fedora OS of version 22 and later):

```
# dnf update
```



If during the update of packages there is an error, uninstall Dr.Web Industrial for UNIX File Servers and install it again. If necessary, see sections [Uninstallation of Dr.Web Industrial for UNIX File Servers installed from the repository](#) and [Installing from the Repository](#) (items for the OS and the package manager that you are using).

#### • DEB packages (apt-get)

1. Change the repository (from the package repository of your current version to the package repository of the recent version).
2. Upgrade the Dr.Web Industrial for UNIX File Servers packages by entering the commands:

```
# apt-get update  
# apt-get dist-upgrade
```



For the Ubuntu 14.04 (64-bit version) OS, the `apt-get dist-upgrade` command may fail. In this case use the aptitude package manager (to upgrade the product, issue the `aptitude dist-upgrade` command).





## Key File Transfer

Regardless of the selected method to upgrade Dr.Web Industrial for UNIX File Servers, your current license [key file](#) (if you have one) will be automatically transferred and installed to the correct location required for the new version.



If any problem occurs during the automatic installation of the key file, you can [install it manually](#).

If a valid license key file was lost, contact the [technical support](#).

## Restoring Connection to the Centralized Protection Server

If it is possible, your connection to the centralized protection server will be restored automatically after the upgrade (if the product had been connected to the centralized protection server before the upgrade). In case the connection has not been automatically restored, then to reestablish the connection of the upgraded Dr.Web Industrial for UNIX File Servers to the anti-virus network, execute the [command](#):

```
$ drweb-ctl esconnect <address> --Certificate <path to the certificate file>
```

In case there are any problems with the connection process, contact the administrator of your anti-virus network.

## Database Update without Internet Connection

In highly secure environments where internet connection is blocked or limited, it is possible to *update virus bases offline*. You need to download updates to a computer connected to the internet, copy them to a USB drive or local network share and then install them to another computer (which is not connected to the internet). The update procedure has to be run from the command line.

### To get the updates

1. Run the command on a computer connected to the internet:

```
$ drweb-ctl update --Path <a path to a directory to store updates>
```

2. Copy the downloaded updates to a USB drive or local network share.
3. Mount the local network share or removable drive on the computer to be updated. If the updates are from the USB drive, run the commands:

```
# mkdir /mnt/usb  
# mount <a path to the device> /mnt/usb
```



4. Apply the updates with the command:

```
$ drweb-ctl update --From /mnt/usb
```

## Uninstalling Dr.Web Industrial for UNIX File Servers

Depending on the method that you used to install Dr.Web Industrial for UNIX File Servers, you can remove the product in one of the following ways.

1. [Start the uninstaller](#) to uninstall the universal package.
2. [Uninstall the packages](#) installed from the Doctor Web repository with the help of the system package manager.



After the uninstalling of Dr.Web Industrial for UNIX File Servers, you need to manually remove the symbolic link to the Dr.Web VFS module from the Samba server directory and to edit the configuration file of Samba (`smb.conf`) by removing the following line from each section that describes a shared directory: `vfs objects = smb_spider` (where `smb_spider` is the name of the symbolic link to the Dr.Web VFS SMB module).

## Uninstalling the Universal Package

Dr.Web Industrial for UNIX File Servers that was installed from the [universal package](#) for UNIX systems can be uninstalled via the command line (if you are using a graphical desktop environment, you will need a terminal emulator for this option).



The uninstallation tool uninstalls not only Dr.Web Industrial for UNIX File Servers, but also all the other Dr.Web products installed on your computer.

If any other Dr.Web products are installed on your computer, besides Dr.Web Industrial for UNIX File Servers, then, to delete only Dr.Web Industrial for UNIX File Servers, use the custom [components installation/removal](#) procedure, instead of running the automatic removal tool.

## Uninstalling Dr.Web Industrial for UNIX File Servers via the Command Line

The uninstallation tool is started by the `uninst.sh` script, which is located in the `<opt_dir>/bin` directory (in GNU/Linux this is `/opt/drweb.com/bin`). Uninstallation procedure of Dr.Web Industrial for UNIX File Servers is described in section [Uninstalling from the Command Line](#).



You can also start the uninstallation tool in silent mode by executing the command:

```
# env DRWEB_NON_INTERACTIVE=yes /opt/drweb.com/bin/uninst.sh
```

In this case, the uninstallation tool is run in silent mode and operates without the user interface (including program dialogs for command-line mode).



Root privileges are required to start the uninstallation tool in silent mode. To elevate the privileges, you can use the `su` and `sudo` commands.



When uninstalling the universal package in OSs using the outdated versions of the package manager (for instance, ALT 8 SP), you may see messages of the following type:

```
/etc/init.d/drweb-configd: No such or directory
```

These messages do not affect the functioning of the system. The uninstallation procedure is performed correctly.

## Uninstalling from the Command Line

Once the command-line-based uninstallation program starts, an offer to remove the product is displayed in the command line.

1. To initiate the removal, enter `Yes` or `Y` in response to the “Do you want to continue?” request. To exit the uninstaller, type `No` or `N`. In this case, removal of Dr.Web products will be canceled.
2. An automatic uninstallation procedure of all installed Dr.Web packages will be launched after you confirm it. During this procedure, information about the removal process will be displayed on the screen and entered into the uninstallation log.
3. Once the process is completed, the uninstallation program will automatically terminate.

## Uninstallation of Dr.Web Industrial for UNIX File Servers Installed from the Repository

See below the procedures for the following OS (package managers):

- [Debian, Mint, Ubuntu \(apt\);](#)
- [ALT Linux, PCLinuxOS \(apt-rpm\);](#)
- [Mageia, OpenMandriva Lx \(urpmi\);](#)
- [Red Hat Enterprise Linux, Fedora, CentOS \(yum, dnf\);](#)



- [SUSE Linux \(zypper\)](#).



All commands mentioned below for package uninstallation require superuser (root) privileges. To elevate the privileges, use the `su` command (to change the current user) or the `sudo` command (to execute the specified command with other user's privileges).

## Debian, Mint, Ubuntu (apt)

To uninstall the root meta-package of Dr.Web Industrial for UNIX File Servers together, enter the command:

```
# apt-get remove drweb-industrial-file-servers
```

If you need to uninstall the root meta-package together with all dependencies, use the `--autoremove` option:

```
# apt-get remove drweb-industrial-file-servers --autoremove
```

To automatically uninstall all packages that are no longer used, enter also the command:

```
# apt-get autoremove
```



### Special Aspects of Uninstallation

1. The first mentioned variant of the command uninstalls only the `drweb-industrial-file-servers` package; any other packages that could have been automatically installed to resolve the dependencies of this package will remain in the system.
2. The second mentioned variant of the command uninstalls all the packages whose name starts with "drweb" (the standard name prefix for Dr.Web products). This command uninstalls all packages with this prefix, not only those of Dr.Web Industrial for UNIX File Servers.
3. The third mentioned variant of the command uninstalls all the packages that have been automatically installed to resolve dependencies of other packages and are no longer necessary (e.g., due to the uninstallation of the dependent packages). This command uninstalls all packages that are not used, not only those of Dr.Web Industrial for UNIX File Servers.

You can also use alternative managers (for example, Synaptic or aptitude) to uninstall packages.

## ALT Linux, PCLinuxOS (apt-rpm)

In this case, uninstalling of Dr.Web Industrial for UNIX File Servers is the same as on Debian and Ubuntu operating systems (see [above](#)).



You can also use alternative managers (for example, Synaptic or aptitude) to uninstall packages.



On ALT 8 SP you may see the following messages appear when the universal package is being uninstalled:

```
/etc/init.d/drweb-configd: No such or directory
```

These messages do not affect the functioning of the system. The uninstallation procedure is performed correctly.

## Mageia, OpenMandriva Lx (urpme)

To uninstall Dr.Web Industrial for UNIX File Servers, enter the command:

```
# urpme drweb-industrial-file-servers
```

To automatically uninstall all packages that are no longer used, enter the command:

```
# urpme --auto-orphans drweb-industrial-file-servers
```



### Special Aspects of Uninstallation

1. The first mentioned variant of the command uninstalls only the `drweb-industrial-file-servers` package; any other packages that could have been automatically installed to resolve the dependencies of this package will remain in the system.
2. The second mentioned variant of the command uninstalls the `drweb-industrial-file-servers` package as well as all the packages that have been automatically installed to resolve dependencies of other packages and are no longer necessary (e.g., due to the uninstallation of the dependent packages).  
This command uninstalls all packages that are not used, not only those of Dr.Web Industrial for UNIX File Servers.

You can also use alternative managers (for example, rpmdrake) to uninstall packages.

## Red Hat Enterprise Linux, Fedora, CentOS (yum, dnf)

To uninstall all the installed Dr.Web packages, enter the command (in certain operating systems, the '\*' character must be escaped: '\\*'):

```
# yum remove drweb*
```



In the Fedora operating system, starting from version 22, it is recommended that instead of manager `yum` the manager `dnf` is used, for example:

```
# dnf remove drweb*
```



#### Special Aspects of Uninstallation

These variants of the command uninstall all the packages whose name starts with "drweb" (the standard name prefix for Dr.Web products).

These commands uninstall all packages with this prefix, not only those of Dr.Web Industrial for UNIX File Servers.

You can also use alternative managers (for example, PackageKit or Yumex) to uninstall packages.

## SUSE Linux (zypper)

To uninstall Dr.Web Industrial for UNIX File Servers, enter the command:

```
# zypper remove drweb-industrial-file-servers
```

To uninstall all the installed Dr.Web packages, enter the command (in certain operating systems, the '\*' character must be escaped: '\\*'):

```
# zypper remove drweb*
```



#### Special Aspects of Uninstallation

1. The first mentioned variant of the command uninstalls only the `drweb-industrial-file-servers` package; any other packages that could have been automatically installed to resolve the dependencies of this package will remain in the system.
2. The second mentioned variant of the command uninstalls all the packages whose name starts with "drweb" (the standard name prefix for Dr.Web products). This command uninstalls all packages with this prefix, not only those of Dr.Web Industrial for UNIX File Servers.

You can also use alternative managers (for example, YaST) to uninstall packages.



## Additional Information

### Dr.Web Industrial for UNIX File Servers Packages and Files

#### Packages

Dr.Web Industrial for UNIX File Servers consists of the following packages:

Package	Contents
drweb-bases	Virus database files
drweb-boost	Boost libraries
drweb-common	<p>The main configuration file—<code>drweb.ini</code>, main libraries, documentation, hierarchy of the Dr.Web Industrial for UNIX File Servers directories, and utility for collection information on product configuration and system environment.</p> <p>During the installation of this package, a user named <code>drweb</code> and a group named <code>drweb</code> are created</p>
drweb-configd	Dr.Web ConfigD Files
drweb-configure	Files of auxiliary tool for Dr.Web Industrial for UNIX File Servers configuration
drweb-ctl	Dr.Web Ctl files
drweb-documentation	Dr.Web for UNIX products documentation files in HTML format
drweb-engine	Dr.Web Virus-Finding Engine scan engine files
drweb-esagent	Files of the Dr.Web ES Agent component
drweb-filecheck	Files of the Dr.Web File Checker component
drweb-industrial-file-servers-doc	PDF Documents
drweb-industrial-file-servers	The root meta-package of Dr.Web Industrial for UNIX File Servers
drweb-httpd	Files of the Dr.Web HTTPD component and of the management web interface (a meta-package)
drweb-httpd-bin	Files of the Dr.Web HTTPD component
drweb-httpd-webconsole	Files of the management web interface



Package	Contents
drweb-icu	Libraries for Unicode support and internationalization
drweb-libs	Main libraries files
drweb-netcheck	Files of the Dr.Web Network Checker component
drweb-openssl	OpenSSL libraries
drweb-protobuf	Google Protobuf libraries
drweb-se	Files of the Dr.Web Scanning Engine component
drweb-smbspider-daemon	Files of the SpIDer Guard for SMB component (the SMB monitoring daemon)
drweb-smbspider	Files of the SpIDer Guard for SMB component
drweb-smbspider-modules	Files of the SpIDer Guard for SMB component (VFS SMB modules)
drweb-smbspider-modules-src	Files of the SpIDer Guard for SMB component (the source code of the VFS SMB module)
drweb-snmpd	Files of the Dr.Web SNMPD component
drweb-spider	Files of the SpIDer Guard component
drweb-update	Files of the Dr.Web Updater component

In the section [Custom Component Installation and Uninstallation](#) there are typical component sets for a custom installation that provide solutions for typical tasks of Dr.Web Industrial for UNIX File Servers.

## Files

After the installation of Dr.Web Industrial for UNIX File Servers, its files are located in the `/opt`, `/etc`, and `/var` directories of the file system.

Structure of the Dr.Web Industrial for UNIX File Servers directories:

Directory	Contents
<ul style="list-style-type: none"><li>• For GNU/Linux: <code>/etc/init.d/</code></li><li>• For FreeBSD: <code>/usr/local/etc/rc.d/</code></li></ul>	<code>drweb-configd</code> script for the Dr.Web ConfigD daemon
<code>&lt;etc_dir&gt;</code>	The <code>drweb.ini</code> configuration file and the <code>drweb32.key</code> key file. In addition, it contains:





Directory	Contents
certs/	– files of certificates in use.
<opt_dir> /	Main directory of Dr.Web Industrial for UNIX File Servers. It contains:
bin/	– executable files of all product components (except for Dr.Web Virus-Finding Engine);
include/	– heading files of libraries in use;
lib/	– libraries in use;
man/	– system help files: man;
share/	– auxiliary product files, including:
doc/	▫ product documentation (readme files, license agreement and administrator guide if packages are already installed),
drweb-bases/	▫ files of Dr.Web virus databases (source files supplied during installation),
scripts/	▫ auxiliary scripts files.
<var_dir> /	Auxiliary and temporary files of, including:
bases/	– files of Dr.Web virus databases (the updated version);
cache/	– cache of updates;
drl/	– the lists of update servers in use;
dws/	– files of a database of web resource categories;
lib/	– the Dr.Web Virus-Finding Engine scan engine as a dynamic-link library (drweb32.dll) and the settings for working in the centralized protection mode;
update/	– directory for a temporary storage of updates during their download.

For details on conventions used for directories, refer to the [Introduction](#).

## Custom Component Installation and Uninstallation

### In this section

- [Typical Component Kits for a Custom Installation](#)
- Dr.Web Industrial for UNIX File Servers Component Installation and Uninstallation:
  - [installed from the repository](#)
  - [installed from the universal package](#)



If necessary, you can choose to install or uninstall only certain Dr.Web Industrial for UNIX File Servers components by installing or uninstalling the respective [packages](#). Perform custom component installation or uninstallation the same way the product was installed.

To reinstall a component, you can uninstall it first and then install again.

## Typical Component Kits for a Custom Installation

If it is required to install Dr.Web Industrial for UNIX File Servers with the limited functionality, instead of installation of the root meta-package from the [repository](#) or from the [universal package](#), you can install only component packages that provide the required functionality. The packages required to resolve dependencies will be automatically installed. The table below displays component sets designed to resolve typical Dr.Web Industrial for UNIX File Servers tasks. In the column **Package for Installation**, there is a list of packages required for installation to obtain the specified component suite.

Custom Component Kit	Packages for Installation	Will be Installed
Minimum kit for console scanning	<ul style="list-style-type: none"><li>• <code>drweb-filecheck</code>,</li><li>• <code>drweb-se</code></li></ul>	<ul style="list-style-type: none"><li>• Dr.Web ConfigD,</li><li>• Dr.Web Ctl,</li><li>• Dr.Web File Checker,</li><li>• Dr.Web Scanning Engine,</li><li>• Dr.Web Updater,</li><li>• Virus databases</li></ul>
Suite for file system monitoring of GNU/Linux	<ul style="list-style-type: none"><li>• <code>drweb-se</code>,</li><li>• <code>drweb-spider</code></li></ul>	<ul style="list-style-type: none"><li>• Dr.Web ConfigD,</li><li>• Dr.Web Ctl,</li><li>• Dr.Web File Checker,</li><li>• Dr.Web Scanning Engine,</li><li>• Dr.Web Updater,</li><li>• SpIDer Guard,</li><li>• Virus database</li></ul>
Suite for monitoring of shared Samba directories	<ul style="list-style-type: none"><li>• <code>drweb-se</code>,</li><li>• <code>drweb-smbspider</code></li></ul>	<ul style="list-style-type: none"><li>• Dr.Web ConfigD,</li><li>• Dr.Web Ctl,</li><li>• Dr.Web File Checker,</li><li>• Dr.Web Scanning Engine,</li><li>• Dr.Web Updater,</li><li>• SpIDer Guard for SMB,</li><li>• Virus database</li></ul>



## Installation and Uninstallation of Dr.Web Industrial for UNIX File Servers Components Installed from Repository

If Dr.Web Industrial for UNIX File Servers is installed from repository, for custom component installation or uninstallation use the respective command of the package manager, used in your OS. For example:

1. To uninstall Dr.Web Network Checker (package `drweb-netcheck`) from Dr.Web Industrial for UNIX File Servers installed on CentOS, use the command:

```
# yum remove drweb-netcheck
```

2. To additionally install Dr.Web Network Checker (package `drweb-netcheck`) to Dr.Web Industrial for UNIX File Servers installed on OS Ubuntu, use the command:

```
# apt-get install drweb-netcheck
```

If needed, use help on package manager used in your OS.

## Installation and Uninstallation of Dr.Web Industrial for UNIX File Servers Components Installed from the Universal Package

If Dr.Web Industrial for UNIX File Servers is installed from the universal package and you want to additionally install or reinstall a package of a component, you will need an installation file (with the `.run` extension), from which Dr.Web Industrial for UNIX File Servers was installed. If you did not save this file, download it from the Doctor Web website.

### Unpacking the Installation File

When you launch the `.run` file, you can also specify the following command-line parameters:

`--noexec`—unpack Dr.Web Industrial for UNIX File Servers installation files instead of starting the installation process. The files will be placed to the directory that is specified in the `TMPDIR` environment variable (usually, `/tmp`).

`--keep`—do not delete Dr.Web Industrial for UNIX File Servers installation files and the installation log automatically after the installation completes.

`--target <directory>`—unpack Dr.Web Industrial for UNIX File Servers installation files to the specified `<directory>`.

For a full list of command-line parameters that can be specified for the launching of the `.run` file, enter the command:

```
$ ./<file_name>.run --help
```



For a custom installation, you need to use the unpacked installation files. If there is no directory containing these files, you should first unpack them. To do that, enter the command:

```
$ ./<file_name>.run --noexec --target <directory>
```

After the command is executed, a nested directory named *<file\_name>* will appear in the directory *<directory>*.

## Custom Installation of the Components

Installation RUN file contains packages of all components of Dr.Web Industrial for UNIX File Servers (in the RPM format) and supporting files. Package files of each component have the following structure:

```
<component_name>_<version>~linux_<platform>.rpm
```

where *<version>* is a string that contains the version and time of the product release, and *<platform>* is a platform for which Dr.Web Industrial for UNIX File Servers is intended. Names of all the packages containing the components of Dr.Web Industrial for UNIX File Servers start with the “drweb” prefix.

Package manager is enabled for the installation of packages to the installation kit. For the custom installation, you should use a service script `installpkg.sh`. To do that, first, you need to unpack the contents of the installation package to a directory.



To install packages, superuser permissions are required (i.e. privileges of the *root* user). To elevate your privileges, use the `su` command for changing the current user or the `sudo` command to execute the specified command with the privileges of another user.

To start installation or reinstallation of a component package, go to the directory which contains the unpacked installation kit, and execute the command via the console (or via a console emulator—terminal for the graphical mode):

```
# ./scripts/installpkg.sh <package_name>
```

For example:

```
# ./scripts/installpkg.sh drweb-netcheck
```

If it is necessary to start the full Dr.Web Industrial for UNIX File Servers installation, launch the automatic installation script. To do that, use the command:

```
$ ./install.sh
```



Besides that, you can install all Dr.Web Industrial for UNIX File Servers packages (to install the missing or accidentally deleted components as well) by launching the installation of the root meta-package:

```
# ./scripts/installpkg.sh drweb-industrial-file-servers
```

## Custom Uninstallation of the Components

For the custom uninstallation of a component, use the appropriate uninstallation command of the package manager of your OS if your OS uses the RPM format of packages:

- in Red Hat Enterprise Linux and CentOS, use the command `yum remove <package_name>;`
- in Fedora, use the command `yum remove <package_name>` or `dnf remove <package_name>;`
- in SUSE Linux, use the command `zypper remove <package_name>;`
- in Mageia, OpenMandriva Lx, use the command `urpme <package_name>;`
- in Alt Linux and PCLinuxOS, use the command `apt-get remove <package_name>.`

For example, for Red Hat Enterprise Linux:

```
# yum remove drweb-netcheck
```

If your OS uses DEB packages (also MSVS 3.0 OS), or if there is no package manager in your system (FreeBSD), for the custom uninstallation, you should use the package manager `zypper`, which is automatically installed within the Dr.Web Industrial for UNIX File Servers installation. To do that, go to the directory `<opt_dir>/bin` (for GNU/Linux—`/opt/drweb.com/bin`) and execute the command:

```
# ./zypper remove <package_name>
```

For example:

```
# ./zypper remove drweb-netcheck
```

If you need to uninstall Dr.Web Industrial for UNIX File Servers, launch the [automatic removal](#) script. To do this, enter the command:

```
# ./uninst.sh
```

To reinstall a component, you can uninstall it first and then install by launching the custom or full installation from the installation kit.



## Configuring Security Subsystems

Presence of the SELinux enhanced security subsystem in the OS as well as the use of mandatory access control systems, such as PARSEC—as opposed to the classical discretionary model used by UNIX—causes problems in the work of Dr.Web Industrial for UNIX File Servers when its default settings are used. To ensure correct operation of Dr.Web Industrial for UNIX File Servers in this case, it is necessary to make additional changes to the settings of the security subsystem and/or to the settings of Dr.Web Industrial for UNIX File Servers.

This section discusses the following settings that ensure correct operation of Dr.Web Industrial for UNIX File Servers:

- [configuring SELinux Security Policies](#),
- [configuring the launch in the CSE \(Closed Software Environment\) mode](#) (OS Astra Linux SE 1.6 and 1.7).



Configuring the permissions of the PARSEC mandatory access control system for Dr.Web Industrial for UNIX File Servers will allow the components of Dr.Web Industrial for UNIX File Servers to bypass the restrictions of the set security policies and to get access to the files that belong to different privilege levels.



Even if you have not configured the permissions of the PARSEC mandatory access control system for Dr.Web Industrial for UNIX File Servers, you still will be able to launch file scanning directly from the [command line](#). To do this, use the `drweb-ctl` [command](#) in the autonomous mode, by specifying the `--Autonomous` option in the command call. When scanning is launched this way, it is possible to scan only those files that can be accessed with the privileges not exceeding those of the user who launched the scanning.

This mode has several features.

- To run an autonomous copy, you need a valid [key file](#), working in the [centralized protection](#) mode is not supported (an option to [install](#) the key file, exported from centralized protection server, is available). In this case, even if Dr.Web Industrial for UNIX File Servers is connected to the centralized protection server, the autonomous copy does not notify the centralized protection server of the threats detected in the autonomous copy mode.
- All additional components that support the functioning of the autonomous copy, will be launched under the current user and will work with specially generated configuration file.
- All temporary files and UNIX sockets are created only in the directory with a unique name, which is created when the autonomous copy is launched. The unique temporary directory is created in the system directory for temporary files (path to this directory is available in the `TMPDIR` environment variable).
- All the required paths to virus databases, the scan engine and executable files used during scanning are defined by default or retrieved from the special environment variables.
- The number of the autonomous copies working simultaneously is not limited.



- When the autonomous copy is terminated, the set of supporting components also terminates.

## Configuring SELinux Security Policies

If your GNU/Linux distribution includes SELinux (*Security-Enhanced Linux*), you may need to configure SELinux security policies to get the servicing components of Dr.Web Industrial for UNIX File Servers (such as the [scan engine](#)) to operate correctly after the installation.

### Universal Package Installation Issues

If SELinux is enabled, installation from the [installation file](#) (`.run`) can fail because an attempt to create the *drweb* user, under which Dr.Web Industrial for UNIX File Servers components operate, can be blocked.

If installation of Dr.Web Industrial for UNIX File Servers from the file fails due to inability to create the *drweb* user, check the SELinux operation mode with the `getenforce` command. The command outputs the current scanning mode:

- *Permissive*—protection is active but a permissive strategy is used: actions that violate the security policy are not denied but information on the actions is logged;
- *Enforced*—protection is active and restrictive strategy is used: actions that violate security policies are blocked and information on the actions is logged;
- *Disabled*—SELinux is installed but not active.

If SELinux is operating in *Enforced* mode, change it to *Permissive*. For that purpose, use the command:

```
# setenforce 0
```

This command (until the next reboot) enables *Permissive* mode for SELinux.



Regardless of the operation mode enabled with the `setenforce` command, after the restart of the operating system, SELinux returns to the safe operation mode specified in the its settings (file with SELinux settings usually resides in the `/etc/selinux` directory).

After the successful Dr.Web Industrial for UNIX File Servers installation, enable the *Enforced* mode again before starting the product. For that, use the command:

```
# setenforce 1
```

### Dr.Web Industrial for UNIX File Servers Operation Issues

In certain cases when SELinux is running, several Dr.Web Industrial for UNIX File Servers components (such as `drweb-se` and `drweb-filecheck`) can not launch, which causes the impossibility of objects scanning and file system monitoring. The sign of the impossibility of



launching these components is the appearance of [119](#) and [120](#) error messages in system log, managed by `syslog` service (typically this log is located in `/var/log/` directory).

When the SELinux security system denies access, such an event is logged. In general, when the audit daemon is used on the system, the log of the audit is stored in the `/var/log/audit/audit.log` file. Otherwise, messages about blocked operations are saved to the general log file (`/var/log/messages` or `/var/log/syslog`).

If the scanning components of the product do not function because they are blocked by SELinux, you will need to compile special *security policies* for them.



Certain GNU/Linux distributions do not feature the utilities mentioned below. If so, you may need to install additional packages with the utilities.

## To Configure SELinux Security Policies

1. Create a new file with the SELinux policy source code (a `.te` file). This file defines restrictions related to the described policy module. The policy source code can be created in one of the following ways.
  - 1) Using the `audit2allow` utility, which is the simplest method. The utility generates permissive rules from messages on access denial in system log files. You can set to search messages automatically or specify a path to the log file manually.



You can use this method only if Dr.Web Industrial for UNIX File Servers components have violated SELinux security policies and these events are registered in the audit log file. If not, wait for such an incident to occur or force-create permissive policies by using the `policygentool` utility (see below).

---

The `audit2allow` utility resides either in the `policycoreutils-python` package or in the `policycoreutils-devel` package (for Red Hat Enterprise Linux, CentOS, Fedora operating systems, depending on the version) or in the `python-sepolgen` package (for Debian and Ubuntu operating systems).

Example of using `audit2allow`:

```
# grep drweb-se.real /var/log/audit/audit.log | audit2allow -M drweb-se
```

In the given example, the `audit2allow` utility performs a search in the `/var/log/audit/audit.log` file to find access denial messages for the `drweb-se` component.

The following two files are created: policy source file `drweb-se.te` and the `drweb-se.pp` policy module ready to install.

If no security violation incidents are found in the system audit log, the utility returns an error message.





In most cases, you do not need to modify the policy file created by the `audit2allow` utility. Thus, it is recommended to go to [step 4](#) for installation of the `drweb-se.pp` policy module.



The `audit2allow` utility outputs invocation of the `semodule` command. By copying the output to the command line and executing it, you complete [step 4](#). Go to [step 2](#) only if you want to modify security policies which were automatically generated for Dr.Web Industrial for UNIX File Servers components.

- 2) Using the `policygentool` utility. For that purpose, specify the name of the component that you want to be treated differently and the full path to its executable file.



The `policygentool` utility included in the `selinux-policy` package for Red Hat Enterprise Linux and CentOS may not function correctly. If so, use the `audit2allow` utility.

Example of policy creation using `policygentool`:

- for the `drweb-se` component:

```
# policygentool drweb-se /opt/drweb.com/bin/drweb-se.real
```

- for the `drweb-filecheck` component:

```
# policygentool drweb-filecheck /opt/drweb.com/bin/drweb-filecheck.real
```

You will be prompted to specify several general properties for created the domain. After that, three files that determine the policy will be created (for each of the components):

`<module_name>.te`, `<module_name>.fc` and `<module_name>.if`.

2. If required, edit the generated policy source file `<module_name>.te` and then use the `checkmodule` utility to create a binary representation (a `.mod` file) of this source file of the local policy.



To ensure successful execution of the command, the `checkpolicy` package must be installed in the system.

Usage example:

```
# checkmodule -M -m -o drweb-se.mod drweb-se.te
```

3. Create a policy module for installation (a `.pp` file) with the help of the `semodule_package` utility.

Example:

```
# semodule_package -o drweb-se.pp -m drweb-se.mod
```

4. To install the created policy module, use the `semodule` utility.



Example:

```
# semodule -i drweb-se.pp
```

For details on SELinux operation and configuration, refer to documentation for your UNIX distribution.

## Configuring the Launch in the CSE Mode (Astra Linux SE 1.6 and 1.7)

The OS Astra Linux SE supports a special *closed software environment* (CSE) mode. In the mode, applications can be launched only if their executable files are signed with the developer digital signature. The developer's public key must be added to the OS list of trusted keys.

By default, Dr.Web Industrial for UNIX File Servers components supplied for Astra Linux SE are signed with the Doctor Web digital signature and the public key for the signature is automatically added to the list of trusted keys during the application installation therefore Dr.Web Industrial for UNIX File Servers should be launched correctly when activating CSE mode in Astra Linux SE 1.5 and earlier versions.

However, in Astra Linux SE 1.6, the signature mechanism has been changed. To launch Dr.Web Industrial for UNIX File Servers in the CSE mode in Astra Linux SE 1.6 and 1.7, configure the OS.

### To Configure Astra Linux SE 1.6 and 1.7 to Launch Dr.Web Industrial for UNIX File Servers in the CSE Mode

1. Install the package `astra-digsig-oldkeys` using the OS installation disk if it is not installed yet.
2. Add the Doctor Web public key to the directory `/etc/digsig/keys/legacy/keys` (if the directory is absent, create it):

```
# cp /opt/drweb.com/share/doc/digsig.gost.gpg /etc/digsig/keys/legacy/keys
```

3. Execute the command:

```
# update-initramfs -k all -u
```

4. Reboot the operating system.



## Getting Started

1. To start using the installed Dr.Web Industrial for UNIX File Servers, you need to [activate](#) it by obtaining and installing a [key file](#).
2. Further scanning of the [operability](#) of Dr.Web Industrial for UNIX File Servers is recommended.
3. Integrate Dr.Web Industrial for UNIX File Servers with the required file services (please, see the [instruction manual for Samba](#)).
4. If necessary, [configure the monitoring parameters](#) for the GNU/Linux file system objects outside the Samba shared directories.
5. Check what components are running and enable additional components, which are disabled by default, if you need them for the protection of your server (for example, the [Dr.Web SNMPD](#), [SpIDer Guard](#) component, depending on the distribution).



You may also need to perform other actions apart from enabling the additional components, for example, you may need to adjust their default configuration.

To view the list of installed and running components and their settings, use one of the following:

- The [command-line-based management tool](#)—Dr.Web Ctl. Use the `drweb-ctl appinfo`, `drweb-ctl cfshow` and `drweb-ctl cfset` commands).
- The management [web interface](#) of Dr.Web Industrial for UNIX File Servers (by default, you can access it via a web browser at `https://127.0.0.1:4443/`).

## Registration and Activation

### In this section

- [Purchasing and Registering License](#)
- [Obtaining Demo License](#)
- [Key File Installation](#)
- [Repeated Registration](#)

### Purchasing and Registering License

After a license is purchased, updates to product components and virus databases are regularly downloaded from Doctor Web update servers. Moreover, if the customer encountered any issue when installing or using the purchased product, they can take advantage of technical support service provided by Doctor Web or its partners.



You can purchase any Dr.Web product as well as obtain a product serial number either from our [partners](#) or our [online store](#). For details on license options, visit the Doctor Web official website at [https://license.drweb.com/license\\_manager](https://license.drweb.com/license_manager).

License registration is required to prove that you are a legal user of Dr.Web Industrial for UNIX File Servers and to activate the functions of the anti-virus, including the regular updates of virus databases. It is recommended that you register the product and activate the license once the installation completes. A purchased license can be activated on the Doctor Web official website at <https://products.drweb.com/register/v4>.

During the activation, it is required to enter the serial number of the purchased license. The serial number is supplied with Dr.Web Industrial for UNIX File Servers or via email when purchasing or renewing the license online.

## Obtaining Demo License

A demo period for your copy of Dr.Web Industrial for UNIX File Servers can be obtained on the Doctor Web official website at <https://download.drweb.com/demoreg/?a=finish&pid=217854>. After you select the product and fill the registration form, you will receive an email with a serial number or key file for Dr.Web Industrial for UNIX File Servers activation.



Another demo period for the same computer can be obtained after a certain time period.

## Key File Installation

The key file is a special file stored on the local computer. It corresponds to the purchased license or activated demo period for Dr.Web Industrial for UNIX File Servers. The file contains information on the provided license or demo period and regulates usage rights in accordance with it.



During Dr.Web Industrial for UNIX File Servers operation, the key file must be located in the default `<etc_dir>` directory (`/etc/opt/drweb.com` for GNU/Linux) under the name `drweb32.key`.

Components of Dr.Web Industrial for UNIX File Servers regularly check whether the key file is available and valid. The key file is digitally signed to prevent its editing. So, the edited key file becomes invalid. It is not recommended to open your key file in text editors in order to avoid its accidental invalidation.

If no valid key file (license or demo) is found, or if the license is expired, operation of the anti-virus components is blocked until a valid key file is installed.

It is recommended that you keep the license key file until it expires, and use it to reinstall Dr.Web Industrial for UNIX File Servers or install it on a different computer. In this case, you



must use the same product serial number and customer data that you provided during the registration.



In email messages, Dr.Web key files are usually transferred packed in zip archives. The archive containing the key file for Dr.Web Industrial for UNIX File Servers activation usually named `agent.zip`. If the message contains *several* archives, then it is necessary to use the `agent.zip` archive.

Before the key file installation, you must unpack the archive in any convenient way and extract the key file from it, saving it to any available directory (for example, to your home directory or to the USB flash drive).

If you have a key file corresponding to the valid license for the product (for example, if you obtained the key file by email or if you want to use Dr.Web Industrial for UNIX File Servers on another server), you can activate Dr.Web Industrial for UNIX File Servers by specifying the path to the key file. For that, do the following:

1. Unpack the key file if archived.
2. Do one of the following:
  - Copy the key file to the `<etc_dir>` directory and rename the file to `drweb32.key` if necessary.
  - In the Dr.Web Industrial for UNIX File Servers [configuration file](#) specify the key file path as the `KeyPath` parameter value.
3. Reload the setting of Dr.Web Industrial for UNIX File Servers by entering the following [command](#):

```
# drweb-ctl reload
```

to apply all changes.

You can also use the [command](#):

```
# drweb-ctl cfset Root.KeyPath <path to the key file>
```

In this case, restart of Dr.Web Industrial for UNIX File Servers is not required. The key file will not be copied to the `<etc_dir>` directory and will remain in its original location.



For details on conventions for `<opt_dir>`, `<etc_dir>`, and `<var_dir>`, refer to the [Introduction](#).

If the key file is not copied to the `<etc_dir>` directory, the user becomes responsible for ensuring that the file is protected from corruption or deletion. This installation method is not recommended as the key file can be accidentally deleted from the system (for example, if the directory, where the key file resides, is periodically cleaned up). Remember that if a key file is lost, you can request the support for a new one, but the number of such requests is limited.



## Repeated Registration

If a key file is lost but the existing license is not expired, you must register again by providing the personal data you specified during the previous registration. You can use a different email address. In this case, the license key file will be sent to the newly specified address.

A license key file can be obtained through the license management command a limited number of times. If that amount has been exceeded, you can confirm the registration of your serial number at <https://products.drweb.com/register/> to receive the key file. The key file is sent to the email that was specified during the first registration.

After the key file is sent to you by email, you need to [install](#) it manually.

## Testing Product Operation

The *EICAR* (European Institute for Computer Anti-Virus Research) test helps testing performance of anti-virus programs that detect viruses using signatures. This test was designed specially so that users could test reaction of newly-installed anti-virus tools to detection of viruses without compromising security of their computers.

Although the *EICAR* test is not actually a virus, it is treated by the majority of anti-viruses as if it were a virus. On detection of this "virus", Dr.Web anti-virus products report the following: EICAR Test File (NOT a Virus!). Other anti-virus tools alert users in a similar way. The EICAR test file is a 68-byte COM-file for MS DOS/MS Windows that outputs the following line on the terminal screen or to the console emulator when executed:

```
EICAR-STANDARD-ANTIVIRUS-TEST-FILE!
```

The EICAR test contains the following character string only:

```
X5O!P%@AP[4\PZX54(P^)7CC)7}$EICAR-STANDARD-ANTIVIRUS-TEST-FILE!$H+H*
```

To create your own test file with the "virus", you may create a new file with the line mentioned above.

If Dr.Web Industrial for UNIX File Servers operates correctly, the test file is detected during a file system scan regardless of the scan type and the user is notified on the detected threat: EICAR Test File (NOT a Virus!).

An example of a command that checks operation of Dr.Web Industrial for UNIX File Servers by means of EICAR test from the command line:

```
$ tail <opt_dir>/share/doc/drweb-se/readme.eicar | grep X5O > testfile &&  
drweb-ctl rawscan testfile && rm testfile
```



This command sets off from the file `<opt_dir>/share/doc/drweb-se/readme.eicar` (supplied with Dr.Web Industrial for UNIX File Servers) a string that represents the body of the EICAR test file, then writes it into a file named `testfile` created in the current directory, then scans the resulting file and removes this file afterwards.



The above-mentioned test requires write access to the current directory. In addition, make sure that it does not contain a file named `testfile` (if necessary, change the file name in the command).

For details on conventions for `<opt_dir>`, `<etc_dir>`, and `<var_dir>`, refer to the [Introduction](#).

If a test virus is detected, the following message is displayed:

```
<path to the current directory>/testfile - infected with EICAR Test File (NOT a Virus!)
```

If an error occurs during the test, refer to the description of known errors (see [Appendix F. Known Errors](#)).



If SpIDer Guard is enabled, a malicious file can be immediately removed or quarantined (depending on the configuration of the component). In this case, the command `rm` will inform that the file is missing, which implies that the monitor operates in normal mode.

## File System Monitoring Setting

### In this section

- [Main File Monitoring Settings](#)
- [Switching Between File Monitoring Modes](#)

To configure the GNU/Linux file system monitoring with the SpIDer Guard monitor, specify values for parameters that are in the `[LinuxSpider]` [settings](#) section of the configuration file.

### Main file monitoring settings

- Enable the monitor by setting the `Start` value to `Yes`.
- Specify the mode of operation with the file system monitor in the `Mode` parameter (it is recommended that you use the `Auto` value).
- If required, in the `ExcludedProc` parameter, list the paths to the executable files of trusted applications, i.e. applications whose access to files will not be controlled by the monitor.



- If required, in the `ExcludedFilesystem` parameter, list the names of file systems (for example, `cifs`) whose files will not be controlled by the monitor.
- Specify the monitoring scope by indicating the set of protected spaces (every protected space is specified by a separate section `[LinuxSpider.Space.<site name>]`). For each space, specify the path to the monitoring directory in the `Path` parameter, and set the `Enable` value to `Yes` to add the space to the monitoring scope.
- In the `ExcludedPath` parameter (for all of the file system combined or for every protected space individually) specify the exclusion scope (the lists of paths to objects monitored and excluded from monitoring). For example, if some paths are controlled by the file server Samba, these paths should be added to the exclusion scope in order to avoid conflicts during the scanning by different monitors.
- Specify the parameters of file scanning and the monitor reaction on detection of various types of threats (if necessary, specify them for every protected space in the monitoring scope individually).

## Changing the file monitoring mode



The enhanced file monitoring modes with their preliminary block are available only if SplDer Guard operates in the `FANOTIFY` mode and the OS kernel is built with the `CONFIG_FANOTIFY_ACCESS_PERMISSIONS` option enabled.

To switch SplDer Guard modes, administrative (root) privileges are required. For that purpose, you use the `su` command to switch the user or the `sudo` command to run as another user.

- To switch SplDer Guard into the `FANOTIFY` mode, use the command:

```
$ sudo drweb-ctl cfset LinuxSpider.Mode FANOTIFY
```

- To change the monitoring mode, use the command:

```
$ sudo drweb-ctl cfset LinuxSpider.BlockBeforeScan <mode>
```

where `<mode>` defines the blocking mode:

- `off`—access is not blocked, SplDer Guard operates in regular (not blocking) monitoring mode;
  - `Executables`—access to executable files is blocked, SplDer Guard enhances monitoring of executable files;
  - `All`—access to all files is blocked, SplDer Guard monitors files in “paranoid” mode.
- To change the period which defines scan results, that Dr.Web File Checker stores in cash, as up to date, use the command:

```
$ sudo drweb-ctl cfset FileCheck.RescanInterval <period>
```





where the *<period>* parameter determines the validity period for scan results, stored in the cache. It can have a value from 0s through 1m. If you set an interval smaller than 1 second, there will be no delay and files will be scanned upon any request.

After all settings are adjusted, restart Dr.Web Industrial for UNIX File Servers, use the [command](#):

```
# drweb-ctl reload
```

You can also restart the configuration daemon Dr.Web ConfigD, use the command:

```
# service drweb-configd restart
```

## Integration with Samba File Server

### In this section

- [Steps for Integration with Samba](#)
- [Configuration Tool](#)



The SplDer Guard for SMB monitor uses a special VFS SMB module for the integration with the Samba server. With SplDer Guard for SMB, several versions of this module are supplied. They are built for various versions of Samba. However, the supplied versions of the VFS SMB module may be incompatible with the version of Samba installed on your file server. It may occur, for example, if your Samba server uses the `CLUSTER_SUPPORT` option.

If VFS SMB modules are incompatible with your Samba server, the *corresponding message* is shown during the Dr.Web Industrial for UNIX File Servers installation. In this case, build the VFS SMB module for your Samba server manually (including the compatibility with the `CLUSTER_SUPPORT` option if necessary).

The procedure of building the VFS SMB module from the supplied source code files is described in the [Building the VFS SMB Module](#) section.

### Steps for Integration with Samba

To integrate SplDer Guard for SMB with the Samba file server, do the following:

1. In the directory from which Samba loads its VFS SMB modules (the default directory in GNU/Linux is `/usr/lib/samba/vfs`), create a symbolic link `smb_spider.so` that points to the Dr.Web-supplied VFS SMB module that corresponds to your version of Samba.

The VFS SMB modules supplied by Dr.Web are stored in the directory with libraries `<opt_dir>/lib/<architecture>-linux-gnu/samba/vfs` (in Debian, Ubuntu, Mint) or `<opt_dir>/lib64/samba/`.

The modules have file names that look as follows: `libsmb_spider.so.<ver>`, where `<ver>` is the version of the Samba server for which the module is intended.



For instance: `/opt/drweb.com/lib/x86_64-linux-gnu/samba/lib smb_spider.so.4.13.0` is a VFS SMB module for the Samba server version 4.13.0 that runs in the GNU/Linux environment, `x86_64` architecture.

2. In the configuration file of the Samba server—`smb.conf` (the default location in GNU/Linux is `/etc/samba`)—create sections for the shared directories. Such a section should look like:

```
[<share name>]
comment = <any comment>
path = <path to the protected directory>
vfs objects = smb_spider
writeable = yes
browseable = yes
guest ok = yes
public = yes
```

where the `<share name>` is any name for the shared resource and `<any comment>` is an arbitrary line with a comment (optional). The object's name specified in `vfs objects` must be similar to the symbolic link (here `smb_spider`).

After that, this directory, specified in `path` parameter, will be monitored by SpIDer Guard for SMB. Interaction between SpIDer Guard for SMB and the VFS SMB module will be performed via a UNIX socket `/<samba chroot path>/var/run/.com.drweb.smb_spider_vfs`. By default, the path to this UNIX socket is specified in the SpIDer Guard for SMB settings and in VFS SMB module settings.

You can connect SpIDer Guard for SMB to customized in Samba server configuration file using the `drweb-configure` configuration tool (see [below](#)).

3. If you need to change the path to the socket, specify the new path both in the [settings](#) of SpIDer Guard for SMB (the `SmbSocketPath` parameter) and in the configuration file of Samba—`smb.conf`. For that, add the following line to the `[<share name>]` section:

```
smb_spider:socket = <path to socket>
```

where `<path to socket>` must be an absolute path to the UNIX socket, relative to the root directory that was set for the Samba server by using `chroot (<samba chroot path>)`.

4. If required, you can use `ExcludedPath` and `IncludedPath` parameters to exclude paths to objects located in the protected shared directories or to include them in SpIDer Guard for SMB checks. You can specify paths to directories or paths to files. If you specify a directory, all content of the directory is skipped or scanned.



The `IncludedPath` parameter takes precedence over the `ExcludedPath` parameter, that is, if the same object (file or directory) is included in both parameter values, this object will be checked.



5. If you need to specify personal scanning settings for this shared directory (different from the default settings used for all shared directories), create a tag identifier for the VFS SMB module that controls this directory:

```
smb_spider:tag = <share name>
```

Then specify personal settings for the protection of this shared directory in SpIDer Guard for SMB settings as a [separate section](#) [SMBSpider.Share.<share name>].

To add a new section identified by a <share name> tag with the help of the Dr.Web Ctl command-line tool, it is necessary to use the following command: `drweb-ctl cfset SmbSpider.Share.<share name>.<parameter> <value>`, for example:

```
# drweb-ctl cfset SmbSpider.Share.UserFiles.OnAdware Quarantine
```

This command adds the [SMBSpider.Share.BuhFiles] section into the configuration file. This added section will contain all the available parameters adjusting the scanning of this shared directory, at that, values for all parameters, except the `OnAdware` parameter specified in the command, will coincide with parameter values from the general [SMBSpider] [section](#).

6. Enable SpIDer Guard for SMB by setting the `Start` value to `Yes`.

After all settings are adjusted, restart both Dr.Web Industrial for UNIX File Servers and the Samba server, use the [command](#):

```
# drweb-ctl reload
```

You can also restart the configuration daemon Dr.Web ConfigD, use the command:

```
# service drweb-configd restart
```



To avoid conflicts between SpIDer Guard for SMB and SpIDer Guard, which may occur in the process of scanning the files located in the shared directories of Samba, it is recommended that you additionally configure SpIDer Guard by performing one of the following actions:

- add Samba shared directories to the exclusion scope (specify these directories in the `ExcludedPath` parameter);
- add the Samba process (`smbd`) to the list of ignored processes (specify `smbd` in the `ExcludedProc` parameter).



## Configuration Tool

For ease of integration SpIDer Guard for SMB with Samba shared directories (connecting and disconnecting them) customized in file server configuration file, a special tool `drweb-configure` was designed. To configure SpIDer Guard for SMB connection to or from a shared directory, use the command:

```
# drweb-configure samba [<parameters>]
```

You can specify the following parameters:

- `+<Samba resource>`—name of Samba shared resource (as it is specified in `smb.conf` configuration file), which should be added to SpIDer Guard for SMB protection;
- `-<Samba resource>`—name of Samba shared resource (as it is specified in `smb.conf` configuration file), which should be excluded from SpIDer Guard for SMB protection;
- `+/all`—adds to SpIDer Guard for SMB protection all shared Samba resources, specified in `smb.conf` configuration file;
- `-/all`—excludes from SpIDer Guard for SMB protection all shared Samba resources, specified in `smb.conf` configuration file;
- `add_symlink`—create a symbolic link `smb_spider.so` pointing to the VFS SMB Dr.Web module (the path to the source file may differ depending on the version of Samba being used);
- `remove_symlink`—remove the symbolic link `smb_spider.so`;
- `<configuration file>`—path to the Samba server configuration file (`smb.conf`), which should be processed. If this argument is skipped, `drweb-configure` tool will attempt to locate the actual `smb.conf` file.



To access help documentation on integrating SpIDer Guard for SMB with Samba shared directories, use the command:

```
$ drweb-configure --help samba
```



## Brief Instructions

### In this section

- Working with File Repositories:
  - [How to Configure GNU/Linux File System Monitoring](#)
  - [How to Connect Dr.Web Industrial for UNIX File Servers to a Samba Server](#)
  - [How to Add a New SMB Shared Directory](#)
- General Operation of Dr.Web Industrial for UNIX File Servers:
  - [How to Restart Dr.Web Industrial for UNIX File Servers](#)
  - [How to Connect to the centralized protection server](#)
  - [How to Disconnect From the Centralized Protection Server](#)
  - [How to Activate Dr.Web Industrial for UNIX File Servers](#)
  - [How to Upgrade Dr.Web Industrial for UNIX File Servers](#)
  - [How To Add or Remove Dr.Web Industrial for UNIX File Servers Component](#)
  - [How to Manage Dr.Web Industrial for UNIX File Servers Component Operation](#)
  - [How to View Log of the Dr.Web Industrial for UNIX File Servers](#)

### How to Connect Dr.Web Industrial for UNIX File Servers to a Samba Server

Follow the instructions provided in the [Integration with Samba File Server](#) section.

### How to Configure GNU/Linux File System Monitoring

Follow the instructions provided in the [File System Monitoring Setting](#) section.



## How to Restart Dr.Web Industrial for UNIX File Servers

To restart Dr.Web Industrial for UNIX File Servers when it is already running, you can also use the script that controls the Dr.Web ConfigD configuration daemon. Startup, stop, or restart of the daemon cause respectively the startup, stop or restart of Dr.Web Industrial for UNIX File Servers.

The shell script that controls the operation of Dr.Web ConfigD is residing in the standard OS directory (for GNU/Linux—`/etc/init.d/`; for FreeBSD—`/usr/local/etc/rc.d/`). The name of the script is `drweb-configd`. It has the following parameters:

Parameter	Description
<code>start</code>	Start Dr.Web ConfigD if it is not running. When Dr.Web ConfigD starts, Dr.Web ConfigD launches all the required components of Dr.Web Industrial for UNIX File Servers.
<code>stop</code>	Shut down Dr.Web ConfigD if it is running. When Dr.Web ConfigD is shutting down, Dr.Web ConfigD also shuts down all the components of Dr.Web Industrial for UNIX File Servers.
<code>restart</code>	Restart (shut down and then start) Dr.Web ConfigD. Dr.Web ConfigD shuts down and then starts all the components of Dr.Web Industrial for UNIX File Servers. If Dr.Web ConfigD is not running, the parameter has the same effect as <code>start</code> .
<code>condrestart</code>	Restart Dr.Web ConfigD only if it is running.
<code>reload</code>	Send a HUP signal to Dr.Web ConfigD if the component is running. Dr.Web ConfigD forwards this signal to all the components of Dr.Web Industrial for UNIX File Servers. The parameter is used to make all components reread their configuration.
<code>status</code>	Output the current state of Dr.Web ConfigD to the console.

For example, to restart Dr.Web Industrial for UNIX File Servers (or start it, if it is not running) in GNU/Linux OS, use the following command:

```
# /etc/init.d/drweb-configd restart
```

## How to Connect to the Centralized Protection Server

1. Obtain the address of the centralized protection server and the file of its certificate from your anti-virus network administrator. You may also need additional parameters, such as an identifier and password for your workstation or identifiers of the main group and tariff group.
2. Use the `esconnect` [command](#) of the [Dr.Web Ctl](#) command-line tool provided with Dr.Web Industrial for UNIX File Servers.



For connection it is required to use the option `--Certificate` by specifying the path to the certificate file of the server. You can additionally enter the identifier of your host (the ID of your “workstation”, if we use the terminology used by the centralized protection server) and a password for authentication on the centralized protection server by using the `--Login` and `--Password` parameters. In this case, connection to the server will be established only if you specify a correct identifier-password pair. If the parameters are not specified, connection to the server will be established only if it is approved on the server (automatically or by the administrator of the anti-virus network, depending on the server settings).

Moreover, you can use the `--Newbie` option (connect as a new user). If this mode is allowed on the server, then after this connection is approved, the server automatically generates a unique identifier/password pair, which will be further used for connection of this agent to the server.



In this mode the centralized protection server generates a new account for the host even if this host already has another account on the server.

A standard example of the command instructing Dr.Web Industrial for UNIX File Servers to connect to the centralized protection server:

```
# drweb-ctl esconnect <server address> --Certificate <path to the certificate file>
```

After establishing a connection to the centralized protection server, Dr.Web Industrial for UNIX File Servers will operate in the centralized protection mode or in the mobile mode, depending on the permissions set on the server and the value of the `MobileMode` [configuration parameter](#) of the Dr.Web ES Agent component. To allow unconditional use of the mobile mode, set the parameter value to `On`. For operation in the centralized protection mode, set the parameter value to `Off`.

A standard example of the command instructing Dr.Web Industrial for UNIX File Servers that is connected to the centralized protection server to switch to the mobile mode is as follows:

```
# drweb-ctl cfset ESAgent.MobileMode On
```



If the centralized protection server does not support or does not allow to use the mobile mode, adjusting the `MobileMode` parameter cannot switch operation of Dr.Web Industrial for UNIX File Servers to the mobile mode.

## How to Disconnect From the Centralized Protection Server

To disconnect Dr.Web Industrial for UNIX File Servers from the centralized protection server and switch its operation into standalone mode, use the `esdisconnect` [command](#) of the [Dr.Web Ctl](#) command-line tool provided in Dr.Web Industrial for UNIX File Servers:

```
# drweb-ctl esdisconnect
```



To use Dr.Web Industrial for UNIX File Servers in standalone mode, a valid license [key file](#) is required. Otherwise, anti-virus functions of Dr.Web Industrial for UNIX File Servers will be *blocked* after the operation is switched to standalone mode.

## How to Activate Dr.Web Industrial for UNIX File Servers

1. Register on Doctor Web website at <https://products.drweb.com/register/v4>.
2. At the email address that you specified during the registration you will receive an archive containing a valid license key file (you can also download this archive directly from the website after you have finished the registration).
3. Carry out the key file [installation procedure](#).

## How to Add a New SMB Shared Directory

1. Edit the configuration file—`smb.conf`—of the Samba server by adding a section describing the shared directory. The section describing the shared directory must be as follows:

```
[<resource name>]
comment = <any comment>
path = <path to the protected directory>
vfs objects = smb_spider
writeable = yes
browseable = yes
guest ok = yes
public = yes
```

where `<share_name>` is any name of the shared resource and `<any comment>` is an arbitrary line with a comment (optional).

2. If you need to specify scanning settings for the added shared directory and these settings differ from the default SpIDer Guard for SMB settings, use steps 3 and 4 of the instruction given in the [Integration with Samba File Server](#) section.
3. Restart the Samba server and Dr.Web Industrial for UNIX File Servers.

## How to Upgrade Dr.Web Industrial for UNIX File Servers

[Update](#) component versions or [upgrade to a new version](#).



During the upgrade you can be asked to remove the current Dr.Web Industrial for UNIX File Servers version.





## How To Add or Remove Dr.Web Industrial for UNIX File Servers Component

Follow the [Custom Component Installation and Uninstallation](#) procedure.



When installing and uninstalling the component, other Dr.Web Industrial for UNIX File Servers components could be additionally installed or uninstalled to resolve dependencies.

## How to Manage Components Operation

To view the status of Dr.Web Industrial for UNIX File Servers components and to manage their operation, you can use:

- The [command-line-based management tool](#) Dr.Web Ctl (use the `drweb-ctl appinfo`, `drweb-ctl cfshow` and `drweb-ctl cfset` commands. To view the list of available management commands, use the command `drweb-ctl --help`).
- The management [web interface](#) of Dr.Web Industrial for UNIX File Servers (by default, you can access it via a web browser at `https://127.0.0.1:4443/`).

## How to View Log of the Dr.Web Industrial for UNIX File Servers

According to default settings the general log of all Dr.Web Industrial for UNIX File Servers components is displayed in `syslog` file (the file for logging messages by the system component `syslog` depends on the system and is located in the directory `/var/log`). General log settings are defined in the [configuration file](#) in the [section](#) [Root] (parameters `Log` and `DefaultLogLevel`). For each [component](#) in their settings section, parameters `Log` and `LogLevel` are available. They set the log storage location and the logging level of messages that the component outputs in the log.

Also you can use the `drweb-ctl log` [command](#).

To change the logging settings, use the Dr.Web Ctl command-line management tool and the Dr.Web Industrial for UNIX File Servers management web interface (if it is installed).

- To identify errors, we recommend you to configure output of the general log of all components to a separate file and enable output of extended debug information to the log. For that, execute the following commands:

```
# drweb-ctl cfset Root.Log <path to log file>
# drweb-ctl cfset Root.DefaultLogLevel DEBUG
```

- To return to the default logging method and verbosity level for all components, execute the following commands:

```
# drweb-ctl cfset Root.Log -r
# drweb-ctl cfset Root.DefaultLogLevel -r
```



## Dr.Web Industrial for UNIX File Servers Components

This section contains a description of the Dr.Web Industrial for UNIX File Servers components. For each of them, you can find information about its functions, operation principles, and parameters stored in the [configuration file](#).

### Dr.Web ConfigD

Dr.Web ConfigD configuration management daemon is the main control component of Dr.Web Industrial for UNIX File Servers. It provides the storage of the configurations of all Dr.Web Industrial for UNIX File Servers components in the centralized environment, manages the operation of all components, and organizes trusted data exchange between them.

The Dr.Web ConfigD configuration management daemon performs the following functions:

- starting and stopping the components of the Dr.Web Industrial for UNIX File Servers depending on settings;
- restarting the components automatically in case of failures;
- starting components upon the request of other components;
- informing the components upon the modification of the settings;
- providing the interface for the centralized management of configuration parameters;
- conveying the information from the license file in use to the components;
- accepting the license information from the components;
- receiving the new license information from the specialized components;
- informing the running components upon the modification of the license information.

### Operating Principles

The Dr.Web ConfigD component is always run as root. It starts the other Dr.Web Industrial for UNIX File Servers components and interacts with them via the preliminarily open socket. The configuration management daemon can accept connections from the other components of the Dr.Web Industrial for UNIX File Servers via the information socket (accessible to all components) and via the managing socket (accessible only to the components run as root). It loads the configuration and the license information from files or from the centralized protection server via the [Dr.Web ES Agent](#). It sets the correct default values for the configuration parameters. By the time when any component starts or receives a `SIGHUP` signal Dr.Web ConfigD has a comprehensive and consistent set of configuration parameters for all Dr.Web Industrial for UNIX File Servers components.

Upon the receipt of a `SIGHUP` signal, Dr.Web ConfigD re-reads the configuration parameters and the license information. If required, the daemon sends to all components notifications instructing them to re-read their configuration.



Upon the receipt of a `SIGTERM` signal, Dr.Web ConfigD shuts down all components and then finishes its own operation. Dr.Web ConfigD also removes all temporary files of the components after they are shut down.

## Component Interaction Principles

1. At startup all components receive the configuration parameters and the license information from Dr.Web ConfigD. Only these parameters are used in further operation.
2. The daemon collects messages from all the controlled components into an integrated log. All information output to `stderr` component is collected by Dr.Web ConfigD and written to the integrated log of Dr.Web Industrial for UNIX File Servers with a mark indicating what component has output this.
3. When shutting down, the controlled components return an exit code. If the code differs from 101, 102, or 103, the configuration daemon restarts this component. Thus, abnormal termination of a component triggers its restart and registration of an error message from `stderr` in the Dr.Web Industrial for UNIX File Servers log.
  - [Code 101](#) is returned when the component cannot operate with the current license. The component will be restarted only after the modification of license parameters.
  - [Code 102](#) is returned when the component cannot operate with the current configuration parameters. Dr.Web ConfigD will try to restart the component when the configuration parameters are modified.
  - Code 103 is returned in case the components started by Dr.Web ConfigD upon request ([Dr.Web Scanning Engine](#) and [Dr.Web File Checker](#)) have been idle for a long time. The period of time after which the component is to shut down is specified in its settings (`IdleTimeLimit` parameter).
  - If the configuration parameters received from the configuration management daemon cannot be applied on the fly, the component exists with code 0 so that Dr.Web ConfigD restart it.
  - If a component cannot connect to the configuration daemon or a communication protocol error occurs, the component outputs an appropriate message to `stderr` and exits with code 1.
4. Signal exchange is organized.
  - Dr.Web ConfigD sends the `SIGHUP` signal to components in order that they apply the modified configuration parameters.
  - Dr.Web ConfigD sends the `SIGTERM` signal to the components so that they shut down. After receiving the signal the component is to shut down in 30 seconds.
  - If a component does not shut down in 30 seconds, Dr.Web ConfigD sends the `SIGKILL` signal to shut it down forcibly.



## Command-Line Arguments

To run the configuration daemon Dr.Web ConfigD, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-configd [<parameters>]
```

The configuration daemon Dr.Web ConfigD can process the following options:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.
--config	<b>Description:</b> Use the specified configuration file for further operation. <b>Short form:</b> -c <b>Arguments:</b> <path to the file>—the path to the configuration file that you want to use.
--daemonize	<b>Description:</b> Run the component in daemon mode. <b>Short form:</b> -d <b>Arguments:</b> None.
--pid-file	<b>Description:</b> Use the specified PID file for further operation. <b>Short form:</b> -p <b>Arguments:</b> <path to the file>—the path to a file into which you would like to the process ID (PID) to be Stored.

### Example:

```
$ /opt/drweb.com/bin/drweb-configd -d -c /etc/opt/drweb.com/drweb.ini
```

The command runs Dr.Web ConfigD as a daemon which uses the following configuration file: /etc/opt/drweb.com/drweb.ini.

## Startup Notes

To enable the operation of Dr.Web Industrial for UNIX File Servers, Dr.Web ConfigD must run as a daemon. During the standard booting, Dr.Web ConfigD starts automatically at the start of the operating system; for this purpose Dr.Web ConfigD comes together with a standard management script `drweb-configd` located in the standard OS directory (for GNU/Linux—/etc/init.d/; for FreeBSD—/usr/local/etc/rc.d/). To manage the operation of the



component, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-configd`.

## Configuration Parameters

The daemon Dr.Web ConfigD uses the configuration parameters which can be found in the [Root] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

The section contains the following parameters:

Parameter	Description
<code>DefaultLogLevel</code> <i>{logging level}</i>	Defines default <a href="#">logging level</a> of event logging <i>for all</i> the Dr.Web Industrial for UNIX File Servers components.  The value of this parameter is used for all the components in the product for which the logging level cannot be set up separately.  Default value: <code>Notice</code>
<code>LogLevel</code> <i>{logging level}</i>	<a href="#">Logging level</a> of event logging for Dr.Web ConfigD.  Default value: <code>Notice</code>
<code>Log</code> <i>{log type}</i>	<a href="#">Logging method</a> of the configuration daemon and logging method of those components for which another value of this parameter is not specified.  Note that upon its initial startup, before the configuration file is read, the configuration daemon uses the following values of the parameter: <ul style="list-style-type: none"><li>• As a daemon (if run with the <code>-d</code> option)—<code>SYSLOG:Daemon</code></li><li>• Otherwise—<code>Stderr</code></li></ul> If a component is working in a background mode (was launched with the <code>-d</code> option from the command line), the <code>Stderr</code> value <i>cannot be used</i> for this parameter.  Default value: <code>SYSLOG:Daemon</code>
<code>PublicSocketPath</code> <i>{path to file}</i>	Path to the socket used for interaction between all the Dr.Web Industrial for UNIX File Servers components.  Default value: <code>/var/run/.com.drweb.public</code>
<code>AdminSocketPath</code> <i>{path to file}</i>	Path to the socket used for interaction between the Dr.Web Industrial for UNIX File Servers components with elevated (administrative) privileges.  Default value: <code>/var/run/.com.drweb.admin</code>



Parameter	Description
CoreEnginePath <i>{path to file}</i>	<p>Path to the dynamic library of the Dr.Web Virus-Finding Engine scan engine.</p> <p>Default value: <code>&lt;var_dir&gt;/lib/drweb32.dll</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/lib/drweb32.dll</code></li><li>• For FreeBSD: <code>/var/drweb.com/lib/drweb32.dll</code></li></ul>
VirusBaseDir <i>{path to directory}</i>	<p>Path to the directory with virus database files.</p> <p>Default value: <code>&lt;var_dir&gt;/bases</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/bases</code></li><li>• For FreeBSD: <code>/var/drweb.com/bases</code></li></ul>
KeyPath <i>{path to file}</i>	<p>Path to the key file (license or demo).</p> <p>Default value: <code>&lt;etc_dir&gt;/drweb32.key</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/etc/opt/drweb.com/drweb32.key</code></li><li>• For FreeBSD: <code>/usr/local/etc/drweb.com/drweb32.key</code></li></ul>
CacheDir <i>{path to directory}</i>	<p>Path to the cache directory (used to hold cache for updates as well as cache for information about scanned files).</p> <p>Default value: <code>&lt;var_dir&gt;/cache</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/cache</code></li><li>• For FreeBSD: <code>/var/drweb.com/cache</code></li></ul>
TempDir <i>{path to directory}</i>	<p>Path to the directory with temporary files.</p> <p>Default value: <i>Path copied from the system environment variable</i> TMPDIR, TMP, TEMP <i>or</i> TMPDIR (the environment variables are searched in this particular order). Otherwise <code>/tmp</code>, if there are no such environment variables.</p>
RunDir <i>{path to directory}</i>	<p>Path to the directory with all PID files of running components and sockets used for interaction between the Dr.Web Industrial for UNIX File Servers components.</p> <p>Default value: <code>/var/run</code></p>
VarLibDir <i>{path to directory}</i>	<p>Path to the directory with libraries used by Dr.Web Industrial for UNIX File Servers components.</p> <p>Default value: <code>&lt;var_dir&gt;/lib</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/lib</code></li><li>• For FreeBSD: <code>/var/drweb.com/lib</code></li></ul>
VersionDir <i>{path to directory}</i>	<p>The path to a directory, where the information on the Dr.Web Industrial for UNIX File Servers components current versions is stored.</p> <p>Default value: <code>&lt;var_dir&gt;/version</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/version</code></li></ul>



Parameter	Description
	<ul style="list-style-type: none"><li>• For FreeBSD: <code>/var/drweb.com/version</code></li></ul>
DwsDir <i>{path to directory}</i>	<p>the parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/dws</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/dws</code></li><li>• For FreeBSD: <code>/var/drweb.com/dws</code></li></ul>
AdminGroup <i>{group name   GID}</i>	<p>Group of users with administrative privileges for Dr.Web Industrial for UNIX File Servers management. These users, in addition to the <i>root</i> superuser, are allowed to elevate privileges of the Dr.Web Industrial for UNIX File Servers components to superuser privileges.</p> <p>Default value: <i>Determined</i> during the Dr.Web Industrial for UNIX File Servers installation.</p>
TrustedGroup <i>{group name   GID}</i>	<p>The parameter is not used.</p> <p>Default value: <code>drweb</code></p>
DebugIpc <i>{Boolean}</i>	<p>Include detailed into the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>). IPC messages show the interaction between the configuration daemon and other components.</p> <p>Default value: <code>No</code></p>
AntispamCorePath <i>{path to file}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/lib/vaderetro.so</code></p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/lib/vaderetro.so</code></li><li>• For FreeBSD: <code>/var/drweb.com/lib/vaderetro.so</code></li></ul>
VersionNotification <i>{Boolean}</i>	<p>Notify a user on availability of updates for the currently installed Dr.Web Industrial for UNIX File Servers version.</p> <p>Default value: <code>Yes</code></p>
UseVxcube <i>{Boolean}</i>	<p>Use Dr.Web vxCube for analyzing email attachments when in the mode of an external filter connected to the MTA.</p> <p>Default value: <code>No</code></p>
VxcubeApiAddress <i>{string}</i>	<p>The domain name (FQDN) or the IP address of the host on which the Dr.Web vxCube API server is running.</p> <p>Default value: <i>(not set)</i></p>
VxcubeApiKey <i>{string}</i>	<p>Dr.Web vxCube API key.</p> <p>Default value: <i>(not set)</i></p>
VxcubeProxyUrl <i>{connection address}</i>	<p>The address of the proxy server used for connecting to Dr.Web vxCube.</p> <p>Only HTTP proxies without authorization are supported.</p>



Parameter	Description
	<p>Possible values: <i>&lt;connection address&gt;</i>—proxy server connection parameters in the following format: <code>http://&lt;host&gt;:&lt;port&gt;</code>, where:</p> <ul style="list-style-type: none"><li>• <i>&lt;host&gt;</i> is the host address of the proxy server (IP address or domain name, i.e. FQDN);</li><li>• <i>&lt;port&gt;</i> is the port to be used.</li></ul> <p>Default value: <i>(not set)</i></p>

## Dr.Web Ctl

### In this section

- [General Information](#)
- [Remote host scanning](#)

### General Information

You can manage operation of Dr.Web Industrial for UNIX File Servers from the command line of the operating system. For that, you can use the special Dr.Web Ctl utility (`drweb-ctl`). You can use it to perform the following operations:

- Start scanning file system objects including boot records.
- Launch of scanning of files on remote network hosts (see note [below](#)).
- Start updating anti-virus components (virus databases, the scan engine, and so on depending on the distribution).
- View and change parameters of the Dr.Web Industrial for UNIX File Servers configuration.
- View the status of the Dr.Web Industrial for UNIX File Servers components and statistics on detected threats.
- Connect to the centralized protection server or disconnect from it.
- View quarantine and manage quarantined objects (via the [Dr.Web File Checker](#) component).
- Connect to the centralized protection server or disconnect from it.

User [commands](#) to control Dr.Web Industrial for UNIX File Servers will only take effect if the [Dr.Web ConfigD](#) configuration daemon is running (by default, it is automatically run on system startup).



Note that some control commands require superuser privileges.

To elevate privileges, use the `su` command (change the current user) or the `sudo` command (execute the specified command with other user privileges).





The `drweb-ctl` tool supports auto-completion of commands for managing Dr.Web Industrial for UNIX File Servers operation if this option is enabled your command shell. If the command shell does not allow auto-completion, you can configure this option. For that purpose, refer to the instruction manual for the used OS distribution.



When shutting down, the tool returns the exit code according to convention for the POSIX compliant systems: 0 (zero)—if an operation is successfully completed, non-zero—if otherwise.

Note that the tool only returns a non-null exit code in the case of internal error (for example, the tool could not connect to a component, the requested operation could not be executed, and so on). If the tool detects and possibly neutralizes a threat, it returns the null exit code, because the requested operation (such as `scan`, and so on) is successfully completed. If you need to define the list of the detected threats and applied actions, analyze the messages displayed on the console.

Codes of all errors are listed in the [Appendix F. Known Errors](#) section.

## Remote host scanning

Dr.Web Industrial for UNIX File Servers allows you to scan files located on remote network hosts for threats. Such hosts can be not only fully-featured computing machines, such as workstations and servers, but also routers, set-top boxes, and other smart devices of the Internet of Things. To perform the remote scanning, the remote host has to provide a remote terminal access via *SSH (Secure Shell)* or *Telnet*. To access the device, you need to know an IP address and a domain name of the remote host, as well as the credentials of the user that can remotely access the system via *SSH* or *Telnet*. This user must have access rights to the scanned files (at least the reading rights).

This function can be used only for detection of malicious and suspicious files on a remote host. Elimination of threats (i.e. isolation in the quarantine, removal, and cure of malicious objects) using remote scanning is impossible. To eliminate the detected threats on the remote host, use administration tools provided directly by this host. For example, for routers and other smart devices, update the firmware; for computing machines, establish a connection (in a remote terminal mode, as one of the options) and perform the respective operations in the file system (remove or move files, etc.), or run the anti-virus software installed on them.

Remote scanning is only performed via the command-line tool `drweb-ctl` (using the [command](#) `remotescan`).



## Command-Line Call Format

### 1. Command Format for Calling the Command-Line Utility to Manage the Product

The call format for the command-line tool which manages Dr.Web Industrial for UNIX File Servers operation is as follows:

```
$ drweb-ctl [<general options> | <command> [<argument>] [<command options>]]
```

where:

- *<general options>*—options that can be applied on startup when the command is not specified or can be applied for any command. Not mandatory for startup;
- *<command>*—command to be performed by Dr.Web Industrial for UNIX File Servers (for example, start scanning, output the list of quarantined objects, and other commands);
- *<argument>*—command argument. Depends on the specified command. It can be missing for certain commands;
- *<command options>*—options for managing the operation of the specified command. They can be omitted for some commands.

### 2. General Options

The following general options are available:

Option	Description
-h, --help	Show general help information and exit. To display the help information on any command, use the following call: <pre>\$ drweb-ctl &lt;command&gt; -h</pre>
-v, --version	Show information on the module version and exit
-d, --debug	Show debug information upon execution of the specified command. It cannot be executed if a command is not specified. Use the call: <pre>\$ drweb-ctl &lt;command&gt; -d</pre>



### 3. Commands

Commands to manage Dr.Web Industrial for UNIX File Servers can be divided into the following groups:

- [Anti-virus scanning](#) commands.
- Commands to [manage updates](#) and operation in the centralized protection mode.
- [Configuration management](#) commands.
- Commands to [manage detected threats and quarantine](#).
- [Information](#) commands.




To request help about this component of the product from the command line, use the following command `man 1 drweb-ctl`.

#### 3.1. Anti-virus Scanning Commands

The following commands to manage anti-virus scanning are available:

Command	Description
<code>scan &lt;path&gt;</code>	<p><b>Purpose:</b> to initiate the scan of the specified file or directory by the file scanning component <a href="#">Dr.Web File Checker</a>.</p> <p><b>Arguments</b></p> <p><code>&lt;path&gt;</code>—path to the file or directory to be scanned (the path can be relative).</p> <p>This argument may be omitted if you use the <code>--stdin</code> or the <code>--stdin0</code> option. To specify several files that satisfy a certain criterion, use the <code>find</code> utility (see <a href="#">Usage Examples</a>) and the <code>--stdin</code> or <code>--stdin0</code> option.</p> <p><b>Options</b></p> <p><code>-a [--Autonomous]</code> runs an autonomous copy of <a href="#">Dr.Web Scanning Engine</a> and <a href="#">Dr.Web File Checker</a> to perform the specified scan, terminating them after it is over. Note that threats detected during autonomous scanning will not be added to the common list of threats detected displayed by <code>threats</code> command (see <a href="#">below</a>), and information on them will not be sent to the centralized protection server, if Dr.Web Industrial for UNIX File Servers is controlled by it.</p> <p><code>--stdin</code>—get the list of paths to scan from the standard input string (<code>stdin</code>). Paths in the list need to be separated by the next line character (<code>\n</code>).</p> <p><code>--stdin0</code>—get the list of paths to scan from the standard input string (<code>stdin</code>). Paths in the list need to be separated by the zero character NUL (<code>\0</code>).</p>




Command	Description
	<div> When using <code>--stdin</code> and <code>--stdin0</code> options, the paths on the list should not contain patterns or regular expressions for a search. We recommend that you use the <code>--stdin</code> and <code>--stdin0</code> options to process a paths list generated by an external utility, for example, <code>find</code> in the <code>scan</code> command (see <a href="#">Usage Examples</a>).</div> <p><code>--Exclude &lt;path&gt;</code>—an excluded path. The path can be relative and contains a file mask (with the following wildcards: '?', '*', as well as symbol classes '[ ]', '[! ]', '[^ ]').</p> <p>Facultative option; can be set more than once.</p> <p><code>--Report &lt;type&gt;</code>—specifies the type of scan report.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• BRIEF—brief report.</li><li>• DEBUG—detailed report.</li><li>• JSON—a serialized report in JSON format.</li></ul> <p>Default value: BRIEF.</p> <p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms.</p> <p>If the value is set to 0, time on scanning is not limited.</p> <p>Default value: 0.</p> <p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ArchiveMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning archives (zip, rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MailMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning files of mailers (pst, tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p>



Command	Description
	<p>Default value: 8.</p> <p><code>--ContainerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, jar-files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MaxCompressionRatio &lt;ratio&gt;</code>—set the maximum compression ratio of scanned objects.</p> <p>The ratio must be at least equal to 2.</p> <p>Default value: 3000.</p> <p><code>--MaxSizeToExtract &lt;size&gt;</code>—specify the maximum size for files enclosed in archives. Files whose size is greater than the value of this parameter will be skipped when scanning. There is no size limit for files in archives by default. The size is specified as a number with a suffix (b, kb, mb, gb). If no suffix is specified, the value is treated as size in bytes.</p> <p>Default value: none.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning.</p> <p>Default value: On.</p> <p><code>--OnKnownVirus &lt;action&gt;</code>—an <a href="#">action</a> to perform upon detection of a known threat by using signature-based analysis.</p> <p>Possible actions: Report, Cure, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnIncurable &lt;action&gt;</code>—an action to perform upon detection an incurable threat or when curing action (Cure) failed.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnSuspicious &lt;action&gt;</code>—an action to perform upon detection of a suspicious object by heuristic analysis.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnAdware &lt;action&gt;</code>—an action to perform upon detection of adware programs.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnDialers &lt;action&gt;</code>—an action to perform upon detection of a dialer.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p>



Command	Description
	<p><code>--OnJokes &lt;action&gt;</code>—an action to perform upon detection of joke software.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnRiskware &lt;action&gt;</code>—an action to perform upon detection of riskware.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnHacktools &lt;action&gt;</code>—an action to perform upon detection of a hacktool.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <div> If threat is detected in a file placed in a container (an archive, an email message, and so on), instead of removing the file (Delete), the tool moves the container to the quarantine (Quarantine).</div> <p><code>--FollowSymlinks</code>—resolve symlinks automatically</p>
<code>bootscan</code> <code>&lt;disk drive&gt;   ALL</code>	<p><b>Purpose:</b> start scanning boot records on the specified disks via the file scan component <a href="#">Dr.Web File Checker</a>. Both MBR and VBR records are scanned.</p> <p><b>Arguments</b></p> <p><code>&lt;disk drive&gt;</code>—path to the block file of a disk device whose boot record you want to scan. You can specify several disk devices separated by spaces. The argument is mandatory. If <code>ALL</code> is specified instead of the device file, all boot records on all available disk devices will be checked.</p> <p><b>Options</b></p> <p><code>-a [--Autonomous]</code> runs an autonomous copy of <a href="#">Dr.Web Scanning Engine</a> and <a href="#">Dr.Web File Checker</a> to perform the specified scan, terminating them after it is over. Note that threats detected during autonomous scanning will not be added to the common list of detected threats displayed by <code>threats</code> command (see <a href="#">below</a>), and information on them will not be sent to the centralized protection server, if Dr.Web Industrial for UNIX File Servers is controlled by it.</p> <p><code>--Report &lt;type&gt;</code>—specifies the type of scan report.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>BRIEF</code>—brief report.</li><li>• <code>DEBUG</code>—detailed report.</li><li>• <code>JSON</code>—a serialized report in JSON format.</li></ul> <p>Default value: <code>BRIEF</code>.</p>




Command	Description
	<p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms. If the value is set to 0, time on scanning is not limited. Default value: 0.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning. Default value: On.</p> <p><code>--Cure &lt;Yes No&gt;</code>—enable or disable attempts to cure detected threats. If the value is set to No, only a notification about a detected threat is displayed. Default value: No.</p> <p><code>--ShellTrace</code>—enable display of additional debug information when scanning a boot record</p>
proscan	<p><b>Purpose:</b> initiates scanning of executables containing the code of currently running system processes with the <a href="#">Dr.Web File Checker</a> component. If a malicious executable file is detected, it is neutralized, and all processes run by this file are forced to terminate.</p> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-a [--Autonomous]</code> runs an autonomous copy of <a href="#">Dr.Web Scanning Engine</a> and <a href="#">Dr.Web File Checker</a> to perform the specified scan, terminating them after it is over. Note that threats detected during autonomous scanning will not be added to the common list of detected threats displayed by <code>threats</code> command (see <a href="#">below</a>), and information on them will not be sent to the centralized protection server, if Dr.Web Industrial for UNIX File Servers is controlled by it.</p> <p><code>--Report &lt;type&gt;</code>—specifies the type of scan report. Allowed values:</p> <ul style="list-style-type: none"><li>• BRIEF—brief report.</li><li>• DEBUG—detailed report.</li><li>• JSON—a serialized report in JSON format.</li></ul> <p>Default value: BRIEF.</p> <p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms. If the value is set to 0, time on scanning is not limited. Default value: 0.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning. Default value: On.</p> <p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine</p>




Command	Description
	<p>and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--OnKnownVirus &lt;action&gt;</code>—an <a href="#">action</a> to perform upon detection of a known threat by using signature-based analysis.</p> <p>Possible actions: Report, Cure, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnIncurable &lt;action&gt;</code>—an action to perform upon detection an incurable threat or when curing action (Cure) failed.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnSuspicious &lt;action&gt;</code>—an action to perform upon detection of a suspicious object by heuristic analysis.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnAdware &lt;action&gt;</code>—an action to perform upon detection of adware programs.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnDialers &lt;action&gt;</code>—an action to perform upon detection of a dialer.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnJokes &lt;action&gt;</code>—an action to perform upon detection of joke software.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnRiskware &lt;action&gt;</code>—an action to perform upon detection of riskware.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnHacktools &lt;action&gt;</code>—an action to perform upon detection of a hacktool.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p>





Command	Description
	<div> Note that if a threat is detected in an executable file, Dr.Web Industrial for UNIX File Servers terminates all processes started by the file.</div>
<code>netscan [&lt;path&gt;]</code>	<p><b>Purpose:</b> start distributed scanning of the specified file or directory via the <a href="#">Dr.Web Network Checker</a> agent for network data scanning. If there are no configured connections to other hosts that are running Dr.Web for UNIX, then the scanning will be done only via the locally-available scan engine (similar to the <code>scan</code> command).</p> <p><b>Arguments</b></p> <p><code>&lt;path&gt;</code>—path to the file or directory which is selected to be scanned.</p> <p>If this argument is omitted, the data received via the input thread <code>stdin</code> is scanned.</p> <p><b>Options</b></p> <p><code>--Report &lt;type&gt;</code>—specifies the type of scan report.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>BRIEF</code>—brief report.</li><li>• <code>DEBUG</code>—detailed report.</li><li>• <code>JSON</code>—a serialized report in JSON format.</li></ul> <p>Default value: <code>BRIEF</code>.</p> <p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms.</p> <p>If the value is set to 0, time on scanning is not limited.</p> <p>Default value: 0.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning.</p> <p>Default value: <code>On</code>.</p> <p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ArchiveMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning archives (zip, rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives will not be scanned.</p>




Command	Description
	<p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MailMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning files of mailers (pst, tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ContainerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, jar-files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MaxCompressionRatio &lt;ratio&gt;</code>—set the maximum compression ratio of scanned objects.</p> <p>The ratio must be at least equal to 2.</p> <p>Default value: 3000.</p> <p><code>--MaxSizeToExtract &lt;size&gt;</code>—specify the maximum size for files enclosed in archives. Files whose size is greater than the value of this parameter will be skipped when scanning. There is no size limit for files in archives by default. The size is specified as a number with a suffix (b, kb, mb, gb). If no suffix is specified, the value is treated as size in bytes.</p> <p>Default value: none.</p> <p><code>--Cure &lt;Yes/No&gt;</code>—enable or disable attempts to cure detected threats.</p> <p>If the value is set to No, only a notification about a detected threat is displayed.</p> <p>Default value: No</p>
<code>flowscan &lt;path&gt;</code>	<p><b>Purpose:</b> start scanning the specified file or directory via <a href="#">Dr.Web File Checker</a> using the “flow” <a href="#">method</a> (normally this method is used internally by <a href="#">SplDer Guard</a>).</p> <div><p>For on-demand scanning of files and directories, it is recommended that you use the <code>scan</code> command.</p></div> <p><b>Arguments</b></p> <p><code>&lt;path&gt;</code>—path to the file or directory which is selected to be scanned.</p> <p><b>Options</b></p> <p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms.</p> <p>If the value is set to 0, time on scanning is not limited.</p>




Command	Description
	<p>Default value: 0.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning.</p> <p>Default value: On.</p> <p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ArchiveMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning archives (zip, rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MailMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning files of mailers (pst, tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ContainerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, jar-files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MaxCompressionRatio &lt;ratio&gt;</code>—set the maximum compression ratio of scanned objects.</p> <p>The ratio must be at least equal to 2.</p> <p>Default value: 3000.</p> <p><code>--OnKnownVirus &lt;action&gt;</code>—an <a href="#">action</a> to perform upon detection of a known threat by using signature-based analysis.</p> <p>Possible actions: Report, Cure, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnIncurable &lt;action&gt;</code>—an action to perform upon detection an incurable threat or when curing action (Cure) failed.</p>



Command	Description
	<p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnSuspicious &lt;action&gt;</code>—an action to perform upon detection of a suspicious object by heuristic analysis.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnAdware &lt;action&gt;</code>—an action to perform upon detection of adware programs.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnDialers &lt;action&gt;</code>—an action to perform upon detection of a dialer.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnJokes &lt;action&gt;</code>—an action to perform upon detection of joke software.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnRiskware &lt;action&gt;</code>—an action to perform upon detection of riskware.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p> <p><code>--OnHacktools &lt;action&gt;</code>—an action to perform upon detection of a hacktool.</p> <p>Possible actions: Report, Quarantine, Delete.</p> <p>Default value: Report.</p>
	<div> If threat is detected in a file placed in a container (an archive, an email message, and so on), instead of removing the file (Delete), the tool moves the container to the quarantine (Quarantine).</div>
<code>rawscan &lt;path&gt;</code>	<p><b>Purpose:</b> start “raw” scanning of the specified file or directory by <a href="#">Dr.Web Scanning Engine</a> directly, without the use of <a href="#">Dr.Web File Checker</a>.</p>




Command	Description
	<div><p>Note that threats detected by “raw” scanning are not included into the list of detected threats that is displayed by the <code>threats</code> command (see <a href="#">below</a>).</p></div> <hr/> <div><p>It is recommended that you use this command only to debug the functioning of Dr.Web Scanning Engine. Note that the command outputs the “cured” status, if at least <i>one</i> threat is neutralized of those threats that are detected in a file (not <i>all</i> threats might be neutralized). Thus, it is <i>not recommended</i> to use this command if you need thorough file scanning. In the latter case it is recommended to use the <code>scan</code> command.</p></div> <div><h3>Arguments</h3><p><code>&lt;path&gt;</code>—path to the file or directory which is selected to be scanned.</p><h3>Options</h3><p><code>--ScanEngine &lt;path&gt;</code>—path to the UNIX socket of the Dr.Web Scanning Engine. If not specified, an autonomous instance of the scan engine is started (which will be shut down once the scanning is completed).</p><p><code>--Report &lt;type&gt;</code>—specifies the type of scan report.</p><p>Allowed values:</p><ul style="list-style-type: none"><li>• BRIEF—brief report.</li><li>• DEBUG—detailed report.</li><li>• JSON—a serialized report in JSON format.</li></ul><p>Default value: BRIEF.</p><p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms.</p><p>If the value is set to 0, time on scanning is not limited.</p><p>Default value: 0.</p><p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p><p>If the value is set to 0, nested objects will be skipped during scanning.</p><p>Default value: 8.</p><p><code>--ArchiveMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning archives (zip, rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives will not be scanned.</p></div>



Command	Description
	<p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MailMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning files of mailers (pst, tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ContainerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, jar-files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MaxCompressionRatio &lt;ratio&gt;</code>—set the maximum compression ratio of scanned objects.</p> <p>The ratio must be at least equal to 2.</p> <p>Default value: 3000.</p> <p><code>--MaxSizeToExtract &lt;size&gt;</code>—specify the maximum size for files enclosed in archives. Files whose size is greater than the value of this parameter will be skipped when scanning. There is no size limit for files in archives by default. The size is specified as a number with a suffix (b, kb, mb, gb). If no suffix is specified, the value is treated as size in bytes.</p> <p>Default value: none.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning.</p> <p>Default value: On.</p> <p><code>--Cure &lt;Yes No&gt;</code>—enable or disable attempts to cure detected threats.</p> <p>If the value is set to No, only a notification about a detected threat is displayed.</p> <p>Default value: No.</p> <p><code>--ListCleanItem</code>—enable outputting the list of clean (non-infected) files found inside a container that was scanned.</p> <p><code>--ShellTrace</code>—enable display of additional debug information when scanning a file.</p> <p><code>--Output &lt;path to file&gt;</code>—duplicate the output of the command to the specified file</p>
<code>remotescan</code> <code>&lt;host&gt; &lt;path&gt;</code>	<p><b>Purpose:</b> initiates scanning of the specified file or directory on the specified remote host by connecting to it via <i>SSH</i> or <i>Telnet</i>.</p>



Command	Description
	<div><p>Note that threats detected by remote scanning will not be neutralized and also will not be included into the list of detected threats that is displayed by the <code>threats</code> command (see <a href="#">below</a>).</p><hr/><p>This function can be used only for detection of malicious and suspicious files on a remote host. To eliminate detected threats on the remote host, it is necessary to use administration tools provided directly by this host. For example, for routers, set-top boxes, and other “smart” devices, a mechanism for a firmware update can be used; for computing machines, it can be done via a connection to them (as an option, using a remote terminal mode) and respective operations in their file system (removal or moving of files, and so on), or via running an anti-virus software installed on them.</p></div> <div><b>Arguments</b><ul style="list-style-type: none"><li>• <code>&lt;host&gt;</code>—IP address or a domain name of the remote host.</li><li>• <code>&lt;path&gt;</code>—path to the file or directory to be scanned (the path must be absolute).</li></ul></div> <div><b>Options</b><p><code>-m [--Method] &lt;SSH Telnet&gt;</code>—remote host connection method (protocol).</p><p>If method is not specified, SSH is used.</p><p><code>-l [--Login] &lt;name&gt;</code>—login (user name) used for authorization on the remote host via the selected protocol.</p><p>If a user name is not specified, there will be an attempt to connect to a remote host on behalf of the user who has launched the command.</p><p><code>-i [--Identity] &lt;path to file&gt;</code>—path to the file containing a private key used for authentication of the specified user via the selected protocol.</p><p><code>-p [--Port] &lt;number&gt;</code>—number of the port on the remote host for connecting via the selected protocol.</p><p>Default value: default port for the selected protocol (22 for SSH, 23 for Telnet).</p><p><code>--ForceInteractive</code>—use the SSH interactive session (only for SSH connections).</p><p><i>Optional feature.</i></p><p><code>--TransferListenAddress &lt;address&gt;</code>—an address, listened to receive files transferred from the remote device for scanning.</p><p>Optional feature. If not indicated, an arbitrary address is used.</p><p><code>--TransferListenPort &lt;port&gt;</code>—a port, listened to receive files transferred from the remote device for scanning.</p></div>



Command	Description
	<p>Optional feature. If not indicated, an arbitrary port is used.</p> <p><code>--TransferExternalAddress &lt;address&gt;</code>—an address specified to the remote device to send files for scanning.</p> <p>Optional feature. If not indicated, use the <code>--TransferListenAddress</code> value, or the outgoing address of the already established session.</p> <p><code>--TransferExternalPort &lt;port&gt;</code>—a port to transfer files for scanning, specified for the remote device.</p> <p>Optional feature. If not indicated, an automatically determined port is used.</p> <p><code>--Password &lt;password&gt;</code>—password used for authentication of a user via the selected protocol.</p> <p>Please note that the password is transferred as a plain text.</p> <p><code>--Exclude &lt;path&gt;</code>—the path to be excluded from scanning. The path can contain a file mask with the following allowed symbols: '?' and '*', as well as the symbol classes '[ ]', '[! ]', '[^ ]'. The path (including the path with the file mask) must be absolute.</p> <p>Facultative option; can be set more than once.</p> <p><code>--Report &lt;type&gt;</code>—specifies the type of scan report.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• BRIEF—brief report.</li><li>• DEBUG—detailed report.</li><li>• JSON—a serialized report in JSON format.</li></ul> <p>Default value: BRIEF.</p> <p><code>--ScanTimeout &lt;number&gt;</code>—specify time-out to scan one file, in ms.</p> <p>If the value is set to 0, time on scanning is not limited.</p> <p>Default value: 0.</p> <p><code>--PackerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning packed objects. A packed object is executable code compressed with special software (UPX, PElOCK, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects. etc. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ArchiveMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning archives (zip, rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p>






Command	Description
	<p>Default value: 8.</p> <p><code>--MailMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning files of mailers (pst, tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--ContainerMaxLevel &lt;number&gt;</code>—set the maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, jar-files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>If the value is set to 0, nested objects will be skipped during scanning.</p> <p>Default value: 8.</p> <p><code>--MaxCompressionRatio &lt;ratio&gt;</code>—set the maximum compression ratio of scanned objects.</p> <p>The ratio must be at least equal to 2.</p> <p>Default value: 3000.</p> <p><code>--MaxSizeToExtract &lt;size&gt;</code>—<i>specify the maximum size for files enclosed in archives. Files whose size is greater than the value of this parameter will be skipped when scanning. There is no size limit for files in archives by default. The size is specified as a number with a suffix (b, kb, mb, gb). If no suffix is specified, the value is treated as size in bytes.</i></p> <p>Default value: none.</p> <p><code>--HeuristicAnalysis &lt;On Off&gt;</code>—enable or disable heuristic analysis during the scanning.</p> <p>Default value: On</p>

### 3.2. Commands to manage updates and operation in the centralized protection mode




The following commands for managing updates are available, as well as commands for operation in the centralized protection mode:

Command	Description
update	<p><b>Purpose:</b> initiates updates of anti-virus components (virus databases, the scan engine, etc., depending on the distribution) from the Doctor Web update servers or the local cloud via <a href="#">Dr.Web MeshD</a>, terminates the updating process if already running, or performs rollback of the latest update to previous versions of the updated files.</p>



Command	Description
	<div> The command has no effect if Dr.Web Industrial for UNIX File Servers is connected to the centralized protection server.</div> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p>-l [--local-cloud] uses the local cloud connected to Dr.Web Industrial for UNIX File Servers to download the updates. If the option is not specified, the updates are downloaded from the Doctor Web update servers (default behavior).</p> <p>--From &lt;path&gt;—apply updates from a specified directory offline.</p> <p>--Path &lt;path&gt;—store files for updating offline in a specified directory; if this directory already has files, then they will be updated.</p> <p>--Rollback—rollback the last update, and restore the previous version of files that have been updated during the last update.</p> <p>--Stop—terminate the running updating process</p>
esconnect <server> [ : <port> ]	<p><b>Purpose:</b> connects Dr.Web Industrial for UNIX File Servers to the specified centralized protection server (for example, Dr.Web Enterprise Server). For details on the operation modes, refer to the <a href="#">Operation Modes</a>.</p> <p><b>Arguments</b></p> <ul style="list-style-type: none"><li>• &lt;server&gt;—IP address or network name of the host on which the centralized protection server is operating. This argument is mandatory.</li><li>• &lt;port&gt;—port number used by the centralized protection server. The argument is optional and should be specified only if the centralized protection server uses a non-standard port.</li></ul> <p><b>Options</b></p> <p>--Certificate &lt;path&gt;—a file path to a certificate of the centralized protection server, the connection to which will be established.</p> <p>--Login &lt;ID&gt;—login (workstation identifier) used for connection to the centralized protection server.</p> <p>--Password &lt;password&gt;—password for connection to the centralized protection server.</p> <p>--Group &lt;ID&gt;—identifier of the group to which the workstation is added on connection.</p> <p>--Rate &lt;ID&gt;—identifier of the tariff group applied to your workstation when it is included in one of the centralized protection server groups (can be specified only together with the --Group option).</p> <p>--Compress &lt;On Off&gt;—enables (On) or disables (Off) forced compression of transmitted data. If not specified, usage of compression is determined by the server.</p>





Command	Description
	<p>--Encrypt &lt;On Off&gt;—enables (On) or disables (Off) forced encryption of transmitted data. If not specified, usage of encryption is determined by the server.</p> <p>--Newbie—connect as a “newbie” (get a new account on the server).</p> <div> This command requires <code>drweb-ctl</code> to be started with <i>root</i> privileges. If necessary, use the <code>su</code> or <code>sudo</code> commands.</div>
esdisconnect	<p><b>Purpose:</b> disconnect Dr.Web Industrial for UNIX File Servers from the centralized protection server and switch its operation to standalone mode.</p> <div> The command has no effect if Dr.Web Industrial for UNIX File Servers already operates in standalone mode.</div> <p><b>Arguments:</b> none.</p> <p><b>Options:</b> none.</p> <div> This command requires <code>drweb-ctl</code> to be started with <i>root</i> privileges. If necessary, use the <code>su</code> or <code>sudo</code> commands.</div>

### 3.3. Configuration Management Commands

The following commands to manage configuration are available:

Command	Description
<code>cfset</code> <code>&lt;section&gt; . &lt;parameter&gt;</code> <code>&lt;value&gt;</code>	<p><b>Purpose:</b> to change the active value of the specified parameter in the current configuration of Dr.Web Industrial for UNIX File Servers.</p> <p><b>Arguments</b></p> <ul style="list-style-type: none"><li>• <code>&lt;section&gt;</code>—name of the configuration file section where the parameter resides. This argument is mandatory.</li><li>• <code>&lt;parameter&gt;</code>—name of the parameter. The argument is mandatory.</li><li>• <code>&lt;value&gt;</code>—new parameter value. This argument is mandatory.</li></ul>



Command	Description
	<div> To specify the parameter value, we use the format <code>&lt;section&gt;.&lt;parameter&gt; &lt;value&gt;</code>. Assignment character '=' is not used here.</div> <p>Note that if you want to indicate several parameter values, you need to repeatedly call the <code>cfset</code> command, as many times as the number of parameter values you want to add. To add a new value to the list of parameter values, you need to use the <code>-a</code> option (see below). You cannot specify the string <code>&lt;parameter&gt; &lt;value 1&gt;, &lt;value 2&gt;</code> as an argument, because the string "<code>&lt;value 1&gt;, &lt;value 2&gt;</code>" will be considered one value of the <code>&lt;parameter&gt;</code>.</p> <p>For description of the configuration file, refer to the section <a href="#">Appendix D. Dr.Web Industrial for UNIX File Servers Configuration File</a>, as well as the documentation page displayed by <code>man 5 drweb.ini</code>.</p> <h3>Options</h3> <p><code>-a [--Add]</code>—do not substitute the current parameter value but add the specified value to the list (allowed only for parameters that can have several values, specified as a list). You should also use this option to when adding a new parameter group identified by a tag.</p> <p><code>-e [--Erase]</code>—do not substitute the current parameter value but remove the specified value from the list (allowed only for parameters that can have several values, specified as a list).</p> <p><code>-r [--Reset]</code>—reset the parameter value to the default. At that, <code>&lt;value&gt;</code> is not required in the command and is ignored if specified.</p> <p>Options are not mandatory. If they are not specified, then the current parameter value (the entire list of values, if the parameter currently holds several values) are substituted with the specified value.</p> <p>For sections that describe the individual parameters for shared directories for <a href="#">SplDer Guard for SMB</a>, using the <code>-r</code> option changes the parameter value in the individual settings section to the value of its parent parameter in the settings section of the component.</p> <p>If you need to add a new <a href="#">parameter section</a> for a Samba <a href="#">shared directory</a> with the <code>&lt;tag&gt;</code> tag, use the following command:</p> <pre>cfset SmbSpider.Share.&lt;tag&gt; -a, for example: cfset SmbSpider.Share.BuhFiles -a</pre> <div> This command requires <code>drweb-ctl</code> to be started with root privileges. If necessary, use the <code>su</code> or <code>sudo</code> commands.</div>



Command	Description
<code>cfshow</code> <code>[ &lt;section&gt; [ . &lt;parameter&gt; ]</code> <code>]</code>	<p><b>Purpose:</b> displays parameters of the current configuration of Dr.Web Industrial for UNIX File Servers.</p> <p>The command to display parameters is specified as follows <code>&lt;section&gt;.&lt;parameter&gt; = &lt;value&gt;</code>. Sections and parameters of non-installed components are not displayed.</p> <p><b>Arguments</b></p> <ul style="list-style-type: none"><li>• <code>&lt;section&gt;</code>—name of the configuration file section parameters of which are to be displayed. The argument is optional. If not specified, parameters of all configuration file sections are displayed.</li><li>• <code>&lt;parameter&gt;</code>—name of the displayed parameter. Optional argument. If not specified, all parameters of the section are displayed. Otherwise, only this parameter is displayed. If a parameter is specified without the section name, all parameters with this name from all of the configuration file sections are displayed.</li></ul> <p><b>Options</b></p> <p><code>--Uncut</code>—display all configuration parameters (not only those used with the currently installed set of components). If the option is not specified, only parameters used for configuration of the installed components are displayed.</p> <p><code>--Changed</code>—display only those parameters whose values differ from the default ones.</p> <p><code>--Ini</code>—display parameter values in the INI file format: at first, the section name is specified in square brackets, then the section parameters listed as <code>&lt;parameter&gt; = &lt;value&gt;</code> pairs (one pair per line).</p> <p><code>--Value</code>—display only value of the specified parameter (the <code>&lt;parameter&gt;</code> argument is mandatory in this case)</p>
<code>reload</code>	<p><b>Purpose:</b> send the <code>SIGHUP</code> signal to the <a href="#">Dr.Web ConfigD</a> configuration daemon.</p> <p>On receiving this signal, the Dr.Web ConfigD configuration daemon rereads the <a href="#">configuration</a> and sends its changes to the Dr.Web Industrial for UNIX File Servers components. Then, the configuration daemon reopens the Dr.Web Industrial for UNIX File Servers log, restarts the components that use virus databases (including the scan engine), and attempts to restart those components which were terminated abnormally.</p> <p><b>Arguments:</b> none.</p> <p><b>Options:</b> none</p>



### 3.4. Commands to Manage Detected Threats and Quarantine

The following commands for managing threats and quarantine are available:

Command	Description
<code>threats</code> <code>[&lt;action&gt; &lt;object&gt;]</code>	<p><b>Purpose:</b> apply the specified action to detected threats, selected by their identifiers. Type of the action is specified by the command option.</p> <p>If the action is not specified, displays information on detected but not neutralized threats. The information on threats is displayed according the format, specified using the optional <code>--Format</code> option. If the <code>--Format</code> option is not specified, for each threat the following information is displayed:</p> <ul style="list-style-type: none"><li>• Identifier assigned to the threat (its ordinal number).</li><li>• The full path to the infected file.</li><li>• Information about the threat (name of the threat, threat type according to the classification used by the Doctor Web company).</li><li>• Information about the file: size, the file owner's user name, the time of last modification.</li><li>• History of operations applied to the threat: detection, applied actions, and so on.</li></ul> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>--Format "&lt;format string&gt;"</code>—displays information on threats in the specified format. The description of format string is <a href="#">below</a>.</p> <p>If this option is specified along with any action options, it is ignored.</p> <p><code>-f [--Follow]</code>—wait for new messages about new threats and display them once they are received (CTRL+C interrupts the waiting).</p> <p>If this option is specified along with any action options, it is ignored.</p> <p><code>--Directory &lt;list of directories&gt;</code>—displays only threats detected in files in directories from <code>&lt;list of directories&gt;</code>.</p> <p>If this option is applied along with any options mentioned below, it is ignored.</p> <p><code>--Cure &lt;threat list&gt;</code>—attempt to cure the listed threats (list threat identifiers separating them with commas).</p> <p><code>--Quarantine &lt;threat list&gt;</code> moves the listed threats to <a href="#">quarantine</a> (list threat identifiers are separated with commas).</p> <p><code>--Delete &lt;threat list&gt;</code>—delete the listed threats (list threat identifiers separating them with commas).</p> <p><code>--Ignore &lt;threat list&gt;</code>—ignore the listed threats (list threat identifiers separating them with commas).</p>



Command	Description
	<p>If you need to apply the action to all detected threats, specify <code>All</code> instead of <code>&lt;threat list&gt;</code>. For example, the command:</p> <pre>\$ drweb-ctl threats --Quarantine All</pre> <p>moves all detected malicious objects to quarantine</p>
<code>quarantine</code> <code>[&lt;action&gt; &lt;object&gt;]</code>	<p><b>Purpose:</b> applies an action to the specified object in <a href="#">quarantine</a>.</p> <p>If an action is not specified, information on quarantined objects and their identifiers together with brief information on original files moved to quarantine is displayed. Information on isolated objects is displayed according a format, specified with optional <code>--Format</code> argument. If the <code>--Format</code> argument is not specified, for every isolated (quarantined) object the following information is displayed:</p> <ul style="list-style-type: none"><li>• Identifier assigned to the quarantined object.</li><li>• The original path to the file, before it was moved to quarantine.</li><li>• The date when the file was put in quarantine.</li><li>• Information about the file: size, the file owner's user name, the time of last modification.</li><li>• Information about the threat (name of the threat, threat type according to the classification used by the Doctor Web company).</li></ul> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-a [--Autonomous]</code> starts a separate instance of the <a href="#">Dr.Web File Checker</a> file scanning component to perform the specified quarantine command and terminate it upon completion.</p> <p>This option can be applied along with any options mentioned below.</p> <p><code>--Format "&lt;format string&gt;"</code>—displays information on quarantined objects in the specified format. The description of format string is <a href="#">below</a>.</p> <p>If this option is specified along with any action options, it is ignored.</p> <p><code>-f [--Follow]</code>—wait for new messages about new threats and display them once they are received (CTRL+C interrupts the waiting).</p> <p>If this option is specified along with any action options, it is ignored.</p> <p><code>--Discovery [&lt;list of directories&gt;]</code> searches for <a href="#">quarantine directories</a> in the specified list of directories and add them to the consolidated quarantine upon detecting a threat. If the <code>&lt;list of directories&gt;</code> is not specified, it searches for quarantine directories in the common locations of the file system (volume mounting points and user home directories).</p>



Command	Description
	<p>This option can be specified not only with the <code>-a (--Autonomous)</code> option (see above), but also with any options/actions listed below. Moreover, if the <code>quarantine</code> command is launched as an autonomous copy, that is, with the <code>-a (--Autonomous)</code> option but without the <code>--Discovery</code> option, then it is equivalent to the call of:</p> <pre>quarantine --Autonomous --Discovery</pre> <p><code>--Delete &lt;object&gt;</code>—delete the specified object from quarantine.</p> <p>Note that objects are deleted from quarantine permanently—this action is irreversible.</p> <p><code>--Cure &lt;object&gt;</code>—try to cure the specified object in the quarantine.</p> <p>Note that even if the object was successfully cured, it will remain in quarantine. To restore the cured object from quarantine, use the <code>--Restore</code> option.</p> <p><code>--Restore &lt;object&gt;</code>—restore the specified object from the quarantine to its original location.</p> <p>Note that this command may require <code>drweb-ctl</code> to be started with root privileges. You can restore the file from quarantine even if it is infected.</p> <p><code>--TargetPath &lt;path&gt;</code>—restores an object from the quarantine to the specified location: either as a file with the name specified here (if the <code>&lt;path&gt;</code> is a path to a file), or just to the specified directory (if the <code>&lt;path&gt;</code> is a path to a directory). A path can be an absolute as well as relative (referring to a current directory).</p> <p>Note that this option can only be used in combination with the <code>--Restore</code> option.</p> <p>As an <code>&lt;object&gt;</code>, specify the object identifier in quarantine. To apply the action to all quarantined objects, specify <code>All</code> instead of <code>&lt;object&gt;</code>. For example, the command:</p> <pre>\$ drweb-ctl quarantine --Restore All --TargetPath test</pre> <p>restores all quarantined objects and puts them in <code>test</code> subdirectory, located in a current directory, from which <code>drweb-ctl</code> command was launched.</p> <p>Note that for the <code>--Restore All</code> variant the additional option <code>--TargetPath</code>, if specified, must set a path to a directory, not a path to a file</p>

## Formatted output for threats and quarantine commands





The output format is defined using the format string, specified as the optional argument `--Format`. The format string must be specified in quotes. The format string can include common symbols (displayed "as is"), as well as special markers, output as certain information. The following markers are available:

1. Common for `threats` and `quarantine` commands:

Marker	Description
<code>%{n}</code>	New string
<code>%{t}</code>	Tabulation
<code>%{threat_name}</code>	The name of detected threat (virus) according Doctor Web classification
<code>%{threat_type}</code>	Threat Type ("known virus", and so on) according Doctor Web classification
<code>%{size}</code>	Original file size
<code>%{origin}</code>	The full name of the original file with path
<code>%{path}</code>	Synonym for <code>%{origin}</code>
<code>%{ctime}</code>	Date/time of original file modifying in "%Y-%b-%d %H:%M:%S" format (for example, "2018-Jul-20 15:58:01")
<code>%{timestamp}</code>	Similar to <code>%{ctime}</code> , but in the <i>UNIX timestamp</i> format
<code>%{owner}</code>	Username of the original file owner
<code>%{rowner}</code>	The remote user owner of the original file (if not applicable or value is unknown it is replaced with ?)

2. Specific for `threats` command:

Marker	Description
<code>%{hid}</code>	The identifier of the threat record in the history of events associated with the threat
<code>%{tid}</code>	The threat identifier
<code>%{htime}</code>	Date/time of the event related to a threat
<code>%{app}</code>	The identifier of the Dr.Web Industrial for UNIX File Servers component which processed a threat
<code>%{event}</code>	The latest event related to a threat: <ul style="list-style-type: none"><li>• <code>FOUND</code>—a threat was detected;</li><li>• <code>Cure</code>—a threat was cured;</li><li>• <code>Quarantine</code>—a file with threat was moved to quarantine;</li><li>• <code>Delete</code>—a file with threat was deleted;</li></ul>



Marker	Description
	<ul style="list-style-type: none"><li>• Ignore—a threat was ignored;</li><li>• RECAPTURED—a threat was detected again by an other component</li></ul>
%{err}	Error message text (if no error is replaced with an empty string)

### 3. Specific for quarantine command:

Marker	Description
%{qid}	The identifier of quarantined object
%{qtime}	Date/time of moving the object to quarantine
%{curetime}	Date/time of curing attempt of the object moved to quarantine (if not applicable or value is unknown it is replaced with ?)
%{cures}	The result of the quarantined object curing attempt: <ul style="list-style-type: none"><li>• cured—a threat is cured;</li><li>• not cured—a threat was not cured or no curing attempts were performed</li></ul>

### Example

```
$ drweb-ctl quarantine --Format "{%{n} %{origin}: %{threat_name} - %{qtime}%{n}}"
```

This command displays quarantine contents as records of the following type:

```
{  
  <path to file>: <threat name> - <date of moving to quarantine>  
}  
...
```

## 3.5. Information Commands

The following information commands are available:

Command	Description
appinfo	<p><b>Purpose:</b> output information on the active Dr.Web Industrial for UNIX File Servers components.</p> <p>The following information is displayed about each component that is currently running:</p> <ul style="list-style-type: none"><li>• Internally-used name.</li><li>• Process identifier GNU/Linux (PID).</li><li>• State (running, stopped, and so on).</li></ul>



Command	Description
	<ul style="list-style-type: none"><li>• Error code, if the work of the component has been terminated because of an error.</li><li>• Additional information (optional).</li></ul> <p>For the configuration daemon (<code>drweb-configd</code>) the following is displayed as additional information:</p> <ul style="list-style-type: none"><li>• The list of installed components—<i>Installed</i>.</li><li>• The list of components which must be launched by the configuration daemon—<i>Should run</i>.</li></ul> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-f [--Follow]</code>—waits for new messages on module status change and display them once such a message is received (CTRL+C interrupts the waiting)</p>
<code>baseinfo</code>	<p><b>Purpose:</b> display the information on the current version of the scan engine and status of virus databases.</p> <p>The following information is displayed:</p> <ul style="list-style-type: none"><li>• Version of the scan engine.</li><li>• Date and time when the virus databases that are currently used were issued.</li><li>• The number of available virus records (in the virus databases).</li><li>• The time of the last successful update of the virus databases and of the scan engine.</li><li>• The time of the next scheduled automatic update.</li></ul> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-l [--List]</code>—displays the full list of downloaded files of virus databases and number of virus records in each file</p>
<code>certificate</code>	<p><b>Purpose:</b> displays contents of the trusted Dr.Web certificate used by Dr.Web Industrial for UNIX File Servers. To save the certificate to the <code>&lt;cert_name&gt;.pem</code> file, you can use the following command:</p> <pre>\$ drweb-ctl certificate &gt; &lt;cert_name&gt;.pem</pre> <p><b>Arguments:</b> none.</p> <p><b>Options:</b> none</p>
<code>events</code>	<p><b>Purpose:</b> viewing of the Dr.Web Industrial for UNIX File Servers events. Apart from that, the command allows you to manage events (mark as read, remove).</p>




Command	Description
	<p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>--Report &lt;type&gt;</code>—specify the type of event report.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>BRIEF</code>—brief report.</li><li>• <code>DEBUG</code>—detailed report.</li><li>• <code>JSON</code>—a serialized report in JSON format.</li></ul> <p><code>-f [--Follow]</code>—waits for new events and displays them upon emergence (CTRL+C interrupts the standby).</p> <p><code>-s [--Since] &lt;date, time&gt;</code>—shows the events that occurred before the specified timestamp (&lt;date, time&gt; is specified as YYYY-MM-DD hh:mm:ss).</p> <p><code>-u [--Until] &lt;date, time&gt;</code>—shows the events that occurred no later than the specified timestamp (&lt;date, time&gt; is specified as YYYY-MM-DD hh:mm:ss).</p> <p><code>-t [--Types] &lt;type list&gt;</code>—shows only events of the specified types (separated by commas).</p> <p>The following event types are available:</p> <ul style="list-style-type: none"><li>• <code>Mail</code>—indicates that a threat has been detected in an email;</li><li>• <code>UnexpectedAppTermination</code>—unexpected shutdown of a component.</li></ul> <p>To view all types of events, use <code>All</code>.</p> <p><code>--ShowSeen</code>—displays of already read events as well.</p> <p><code>--Show &lt;list of events&gt;</code>—displays the listed events (event identifiers are separated by commas).</p> <p><code>--Delete &lt;list of events&gt;</code>—removal of listed events (event identifiers are separated by commas).</p> <p><code>--MarkAsSeen &lt;list of events&gt;</code>—marks the listed events as read (event identifiers are separated with a comma).</p> <p>If you want to mark as “read” or delete all events, specify <code>All</code> instead of &lt;events list&gt;. For example, the command:</p> <pre>\$ drweb-ctl events --MarkAsSeen All</pre> <p>will mark as “read” all existing events</p>
<code>report &lt;type&gt;</code>	<p><b>Purpose:</b> create a report on Dr.Web Industrial for UNIX File Servers events in the HTML format (the page body is output to the specified file).</p>



Command	Description
	<p><b>Arguments</b></p> <p><i>&lt;type&gt;</i>—event type that required reporting (indicate one type). See possible values in the <code>--Types</code> option description of the <code>events</code> command above. A mandatory argument.</p> <p><b>Options</b></p> <p><code>-o [--Output] &lt;path to file&gt;</code>—save the report to the specified file. The option is mandatory.</p> <p><code>-s [--Since] &lt;date, time&gt;</code>—reports events that occurred no earlier than the specified timestamp (<i>&lt;date, time&gt;</i> is specified as YYYY-MM-DD hh:mm:ss).</p> <p><code>-u [--Until] &lt;date, time&gt;</code>—reports the events that occurred no later than the specified timestamp (<i>&lt;date, time&gt;</i> is specified as YYYY-MM-DD hh:mm:ss).</p> <p><code>--TemplateDir &lt;path to directory&gt;</code>—a path to the directory that contains HTML report templates.</p> <p>Options <code>-s</code>, <code>-u</code>, and <code>--TemplateDir</code> are not mandatory. For example, the following command:</p> <pre>\$ drweb-ctl report Mail -o report.html</pre> <p>generates a report on all existing email message threat detection events, based on the default template, and saves the result in the <code>report.html</code> file in the current directory</p>
license	<p><b>Purpose:</b> show the information about the currently active license, or get the key file for a license that has already been registered (for example, that has been registered on the company website).</p> <p>If no options are specified, then the following information is displayed (if you are using a license for the standalone mode):</p> <ul style="list-style-type: none"><li>• License number.</li><li>• Date and time when the license expires.</li></ul> <p>If you are using a license provided to you by the centralized protection server (for the use of the product in the centralized protection mode or in the mobile mode), then the appropriate message will be displayed.</p> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>--GetRegistered &lt;serial number&gt;</code>—get a license key file for the specified serial number, if the conditions for the provision of a new key file have not been breached (for example, breached by using the product not in the centralized protection mode, when the license is managed by a centralized protection server).</p>



Command	Description
	<p><code>--Proxy http://&lt;username&gt;:&lt;password&gt;@&lt;server address&gt;:&lt;port number&gt;</code>—get a license key file through a proxy server (used only with the <code>--GetRegistered</code> option).</p> <p>For further information on licensing of Dr.Web products, refer to the <a href="#">Licensing</a> section.</p> <div> To register a serial number, an internet connection is required.</div>
log	<p><b>Purpose:</b> displays the latest log records of Dr.Web Industrial for UNIX File Servers on console screen (in the <code>stdout</code> thread), similar to <code>tail</code> command.</p> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-s [--Size] &lt;number&gt;</code>—the number of the last log records that are to be displayed on a screen.</p> <p><code>-c [--Components] &lt;components list&gt;</code>—the list of component identifiers, which records are displayed. Identifiers are defined with comma separation. If the argument is not defined, all available records logged by all components are displayed.</p> <p>Actual identifiers of the components installed (e.g. internal components names, displayed in log) you can define by using the <code>appinfo</code> command (see above).</p> <p><code>-f [--Follow]</code>—waits for new messages in log and display them once such a message is received (interrupt waiting by pressing CTRL+C)</p>
stat	<p><b>Purpose:</b> Output statistics about the operation of components that process files or about the operation of the network data scanning agent <a href="#">Dr.Web Network Checker</a> (pressing CTRL+C or Q interrupts the statistics display).</p> <p>The statistics output includes:</p> <ul style="list-style-type: none"><li>• name of the component that initiated scanning.</li><li>• PID of the component.</li><li>• average number of files processed per second during the last minute, 5 minutes, 15 minutes.</li><li>• usage percentage of the scanned files cache.</li><li>• average number of scan errors per second.</li></ul> <p>For the distributed scanning agent, the following information is output:</p> <ul style="list-style-type: none"><li>• list of local clients that initiated scanning.</li><li>• list of remote hosts that received files for scanning.</li><li>• list of remote hosts that sent files for scanning.</li></ul> <p>For local clients of the distributed scanning agent, their PID and name are specified; for remote clients—address and port of the host.</p>



Command	Description
	<p>For both clients—local and remote—the following information is output:</p> <ul style="list-style-type: none"><li>• average number of files scanned per second.</li><li>• average number of sent and received bytes per second.</li><li>• average number of errors per second.</li></ul> <p><b>Arguments:</b> none.</p> <p><b>Options</b></p> <p><code>-n [--netcheck]</code> outputs statistics on operation of the network data scanning agent</p>

## Usage Examples

This section contains examples of using the Dr.Web Ctl (`drweb-ctl`) utility:

- Object Scanning:
  - [Simple Scanning Commands](#)
  - [Scanning of Files Selected by Criteria](#)
  - [Scanning of Additional Objects](#)
- [Configuration Management](#)
- [Threats Management](#)
- [An Example of Operation in the Autonomous Copy Mode](#)

### 1. Object Scanning

#### 1.1. Simple Scanning Commands

1. Perform scanning of the `/home` directory with default parameters:

```
$ drweb-ctl scan /home
```

2. Scan paths listed in the `daily_scan` file (one path per line):

```
$ drweb-ctl scan --stdin < daily_scan
```

3. Perform scanning of the boot record on the `sda` drive:

```
$ drweb-ctl bootscan /dev/sda
```

4. Perform scanning of the running processes:

```
$ drweb-ctl procsan
```



## 1.2. Scanning of Files Selected by Criteria

Examples for file selection for scanning are listed below and use the result of the `find` utility operation. The obtained list of files is sent to the `drweb-ctl scan` command with the `--stdin` or `--stdin0` parameter.

1. Scan listed files returned by the utility `find` and separated with the NUL ('\0') character:

```
$ find -print0 | drweb-ctl scan --stdin0
```

2. Scan all files in all directories, starting from the root directory, on one partition of the file system:

```
$ find / -xdev -type f | drweb-ctl scan --stdin
```

3. Scan all files in all directories, starting from the root directory, with the exception of the `/var/log/messages` and `/var/log/syslog` files:

```
$ find / -type f ! -path /var/log/messages ! -path /var/log/syslog |  
drweb-ctl scan --stdin
```

4. Scan all files of the `root` user in all directories, starting from the root directory:

```
$ find / -type f -user root | drweb-ctl scan --stdin
```

5. Scan files of the `root` and `admin` users in all directories, starting from the root directory:

```
$ find / -type f \( -user root -o -user admin \) | drweb-ctl scan --stdin
```

6. Scan files of users with UID in the range 1000–1005 in all directories, starting from the root directory:

```
$ find / -type f -uid +999 -uid -1006 | drweb-ctl scan --stdin
```

7. Scan files in all directories, starting from the root directory, with a nesting level not more than five:

```
$ find / -maxdepth 5 -type f | drweb-ctl scan --stdin
```

8. Scan files in a root directory ignoring files in subdirectories:

```
$ find / -maxdepth 1 -type f | drweb-ctl scan --stdin
```

9. Scan files in all directories, starting from the root directory, with following all symbolic links:

```
$ find -L / -type f | drweb-ctl scan --stdin
```

10. Scan files in all directories, starting from the root directory, without following symbolic links:

```
$ find -P / -type f | drweb-ctl scan --stdin
```





11. Scan files created not later than May 1, 2017 in all directories, starting with the root directory:

```
$ find / -type f -newermt 2017-05-01 | drweb-ctl scan --stdin
```

### 1.3. Scanning of Additional Objects

1. Scanning of objects located in the directory `/tmp` on the remote host `192.168.0.1` by connecting to it via SSH as a user `user` with the password `passw`:

```
$ drweb-ctl remotescan 192.168.0.1 /tmp --Login user --Password passw
```

## 2. Configuration Management

1. Display information on a current Dr.Web Industrial for UNIX File Servers package, including information about running components:

```
$ drweb-ctl appinfo
```

2. Output all parameters from the `[Root]` section of the active configuration:

```
$ drweb-ctl cfshow Root
```

3. Set 'No' as the value of the `Start` parameter in the `[LinuxSpider]` section of the active configuration (this will disable the SpIDer Guard file system monitor):

```
# drweb-ctl cfset LinuxSpider.Start No
```

Note that superuser privileges are required to perform this action. To elevate the privileges, you can use the `sudo` command, as shown in the following example:

```
$ sudo drweb-ctl cfset LinuxSpider.Start No
```

4. Force update of anti-virus components of Dr.Web Industrial for UNIX File Servers:

```
$ drweb-ctl update
```

5. Restart the component configuration of Dr.Web Industrial for UNIX File Servers:

```
# drweb-ctl reload
```

Note that superuser privileges are required to perform this action. To elevate the privileges, you can use the `sudo` command, as shown in the following example:

```
$ sudo drweb-ctl reload
```

6. Connect Dr.Web Industrial for UNIX File Servers to the [centralized protection](#) server operating on host `192.168.0.1` if the server certificate is located in the file `/home/user/cscert.pem`:



```
$ drweb-ctl esconnect 192.168.0.1 --Certificate /home/user/cscert.pem
```

7. Connect Dr.Web Industrial for UNIX File Servers to the [centralized protection](#) server using the `install.cfg` configuration file:

```
$ drweb-ctl esconnect --cfg <path to the install.cfg file>
```

8. Disconnecting Dr.Web Industrial for UNIX File Servers from the centralized protection server:

```
# drweb-ctl esdisconnect
```

Note that superuser privileges are required to perform this action. To elevate the privileges, you can use the `sudo` command, as shown in the following example:

```
$ sudo drweb-ctl esdisconnect
```

9. View the last log records made by the `drweb-update` and `drweb-configd` components in the Dr.Web Industrial for UNIX File Servers log:

```
# drweb-ctl log -c Update,ConfigD
```

### 3. Threats Management

1. Display information on detected threats:

```
$ drweb-ctl threats
```

2. Move all files containing threats which were not neutralized to quarantine:

```
$ drweb-ctl threats --Quarantine All
```

3. Display list of files moved to quarantine:

```
$ drweb-ctl quarantine
```

4. Restore all files from quarantine:

```
$ drweb-ctl quarantine --Restore All
```

### 4. An Example of Operation in the Autonomous Copy Mode

1. Scan files and process quarantine in the autonomous copy mode:

```
$ drweb-ctl scan /home/user -a --OnKnownVirus=Quarantine  
$ drweb-ctl quarantine -a --Delete All
```

The first command will scan files in the `/home/user` directory in the autonomous copy mode. Files containing known viruses will be moved to quarantine. The second command will process quarantine content (in the autonomous copy mode as well) and remove all the objects.



## Configuration Parameters

The Dr.Web Ctl tool for managing the product from the command line does not have its own section with its parameters in the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers. It uses the parameters specified in the [Root] [section](#) of the configuration file.



## Dr.Web Web Management Interface

In this section:

- [Function.](#)
- [Managing the Components.](#)
- [Threats Management.](#)
- [Managing the Settings.](#)
- [Scanning Local Files.](#)

### Function

The web interface of Dr.Web Industrial for UNIX File Servers allows you to:

1. View the current state of the Dr.Web Industrial for UNIX File Servers components, start or stop some of the components.
2. View the status of updates and start an updating process manually, if required.
3. View the status of the product license and load a license key, if required.
4. View the list of detected threats and manage quarantined objects (threats detected in local file system via the [Dr.Web File Checker](#) component are displayed only).
5. Edit the settings of the components included in Dr.Web Industrial for UNIX File Servers.
6. Connect Dr.Web Industrial for UNIX File Servers to the centralized protection server or switch to the standalone mode.
7. Start an on-demand scanning of local files (including a capability to do it by dragging and dropping files onto the page opened in your browser).

### System Requirements of the Web Interface

Correct operation of the web interface is guaranteed for the following web browsers:

- Microsoft Internet Explorer—version 11 and later.
- Mozilla Firefox—version 25 and later.
- Google Chrome—version 30 and later.

### Accessing the Web Interface

To access the web interface, type in the address bar of your browser the following address:

```
https://<host_with_drweb>:<port>/
```

where *<host\_with\_drweb>* is the IP address or the name of the host where Dr.Web Industrial for UNIX File Servers operates with the Dr.Web HTTPD web interface server, and *<port>* is the port



(on this host) which Dr.Web HTTPD is listening on. To access Dr.Web Industrial for UNIX File Servers component which operates on the local host, use IP address `127.0.0.1` or the name `localhost`. By [default](#), the `<port>` is `4443`.

Thus, to access the web interface on the local host by default, enter the following URL in the browser address bar:

```
https://127.0.0.1:4443/
```

After the connection to the managing server is established, the startup page opens and displays the authentication form. To access management functions, fill in the authentication form by specifying the login and password of a user who has administrative privileges on the host where Dr.Web Industrial for UNIX File Servers operates.

If you need, you can provide the authorization on the web interface using a personal user certificate. To do so:

1. Create a personal certificate signed by a certificate authority certificate.
2. Import the signed certificate as a user authorization certificate in the browser that is used to connect to the web interface for management.
3. In the Dr.Web HTTPD [settings](#) (parameter `AdminSSLCA`), specify a path to the certificate authority certificate that signs your personal certificate.

If you use a personal user certificate for the authorization on the web interface, the authorization form does not appear, the user is authorized as `root`.

If necessary, refer to the [Appendix E. Generating SSL certificates](#) section.

## Main Menu

In the left pane of the web interface, which appears once you have successfully passed authentication, there is a main menu, the items in which allow you to do the following:

- **Main** opens the [main page](#) which displays the full list of installed components of Dr.Web Industrial for UNIX File Servers and their status.
- **Threats** opens a page which [displays all the threats](#) detected on the server. In this section, you can manage these detected threats (for example, move infected objects to quarantine, rescan, cure or delete detected malicious objects).
- **Settings** opens a page with the [component settings](#) of Dr.Web Industrial for UNIX File Servers installed on the server.
- **Information** opens a page that shows brief information about the version of this web interface and about the state of virus databases.
- **Help** opens a new browser tab with help information on the Dr.Web for UNIX products.
- **Scan File** displays a panel for quick [file scanning](#), which will stay available on top of any opened page of the web interface until you close this panel.






- **Log Out** ends the current web interface session (not available for authentication with user's personal certificate).


## Managing the Components

You can view the list of components included in Dr.Web Industrial for UNIX File Servers and manage their operation on the **Main** page.


The listed Dr.Web Industrial for UNIX File Servers components are divided into two groups: main components, which monitor threats, and service components, which are responsible for the overall correct operation of Dr.Web Industrial for UNIX File Servers. The list of main components is displayed as a table in the upper part of the page (the list of components depends on the scope of distribution). For each component the following information is specified:

1. **Name.** Click the name to open the [settings page](#) containing the settings for this component;
2. **State.** The state of a component is indicated by a switch icon and by a note about the component current state. To start a component or to suspend its operation, you only need to click its switch. The possible states of the switch are:

	—the component is disabled and is not used;
	—the component is enabled and works correctly;
	—the component is enabled but is not working because of an error.

If an error occurred in the operation of a component, instead of a note about the component state an error message is displayed. If you click the  icon, a window will pop up with detailed information about the error that occurred and with recommendations for resolving this error.

3. **Load.** The average numbers of files processed by the component per second within the last minute, 5 minutes, 15 minutes respectively are specified (displayed as three numbers separated with forward slashes "/").
4. **Errors.** The average numbers of errors encountered by the component per second within the last minute, 5 minutes, 15 minutes respectively are specified (displayed as three numbers separated with forward slashes "/").

To display a tooltip, place the cursor over the  icon.

Below the table, which provides information about main components, you will find service Dr.Web Industrial for UNIX File Servers components (such as the [the scan engine](#), [the file scanning component](#), and so on) listed as a set of tiles. For each service component, its state and operational statistics are also displayed. To open the settings page of any of these components, click the name of a required component. As a rule, these components are started and stopped automatically when needed. If any of them may be started and stopped manually by the user, then, besides the name and the operational statistics, a switch for starting and stopping the component will be displayed on the tile of any such service component.



The bottom of the page displays whether the virus databases are up to date and [license](#) information. To force a virus database update, click **Update**. By clicking the **Renew** button (or the **Activate license** button, depending on the current state of your license) you can renew or activate a license by uploading a valid key file that is appropriate for your Dr.Web Industrial for UNIX File Servers to the licensing server.

## Threats Management

You can view the list of detected threats and manage the reaction to them on the **Threats** page.

This page contains the full list of threats detected by the components of Dr.Web Industrial for UNIX File Servers that monitor and scan the file system. In the upper part of the page, you can see a menu which allows filtering the threats by their category:

- **All**—show all detected threats (including both active and quarantined threats).
- **Active**—show only active threats; i.e. detected but not neutralized yet.
- **Blocked**—show all blocked threats, that is, threats that were not neutralized, but for which the infected objects containing them were blocked (only for file storages monitored by SpIDer Guard for SMB).
- **Quarantined**—show threats that were moved to quarantine.
- **Errors**—show threats that were not processed because of an error.

Just next to each name of a threat category (to its right) in the upper menu, the quantity of detected threats that fall into this category is displayed. The currently selected category, for which the threats belonging to it are currently displayed, is emphasized in a darker font. To display threats of a required category, click the name of the category in the menu.

For each threat, the following information is listed:

- **File**—name of the file that contains a malicious object (file path is not specified).
- **Owner**—name of the user who owns the infected file.
- **Component**—name of the component of Dr.Web Industrial for UNIX File Servers that detected the threat.
- **Threat**—name of the threat that was detected in the file (according to the classification used by the Doctor Web company).

For any object selected in the list, the following information is displayed:

- Name of the threat (displayed as a link that opens a page of the Dr.Web virus information library with the threat description).
- File size, in bytes.
- Name of the component that detected the threat.
- Date and time when the threat was detected.
- Date and time when the threat was last modified.



- Name of the user who owns the infected file.
- Name of the group that includes the file owner.
- Name of the user who uploaded the file to the file server (only for file storages monitored by SpIDer Guard for SMB).
- Identifier that was assigned to the quarantined file containing a threat (if the file was quarantined).
- Full path that points to the original location of the file (where the file was located at the moment of threat detection).

You can select any object in the list by clicking on it. To select multiple objects, select the check boxes for the corresponding objects. To select all objects or cancel the selection, select the check box in the **File** field in the threat list header.

To apply actions to objects selected in the list, click the corresponding button on the toolbar, which is located directly above the threat list. The toolbar contains the following buttons (note that some of them can be unavailable depending on the type of selected threats):

	—remove (i.e. to permanently delete) selected files.
	—restore selected files from quarantine to the original location.
	<p>—apply an additional action to the selected files (available actions are specified in the drop-down list):</p> <ul style="list-style-type: none"><li>• <b>Quarantine</b>—put the selected files that contain threats to quarantine</li><li>• <b>Cure</b>—try to cure the threats</li><li>• <b>Ignore</b>—ignore the threats detected in selected files and to remove the threats from the list</li></ul>

You can also filter displayed threats based on a search query. To filter unnecessary threats out and display only those that correspond to the query, use the search box. The box is displayed on the right side of the toolbar and is marked with . To filter the threat list, enter a word in the search box. All threats that do not have the entered word in their name or description, will be hidden (this filtering is not case-sensitive). To clear search results and display the unfiltered list, click in the search box or erase the word.

## Managing the Settings

You can view and change current [configuration parameters](#) of the components included in Dr.Web Industrial for UNIX File Servers and listed on the [main page](#). For that, open the **Settings** page. On this page, you can also switch Dr.Web Industrial for UNIX File Servers into the *centralized protection* mode or into the *standalone* mode (for further information about these modes please refer to [Operation Modes](#)).

On the left side of the page, a menu is displayed, which contains the names of all the Dr.Web Industrial for UNIX File Servers components whose settings can be viewed and adjusted. To





view and adjust the settings of any component, first click on the name of a desired in this menu. The name of the component whose settings you are currently viewing and editing will be highlighted in this menu on the left.

- The **Centralized protection** item in the menu will take you to the [page for managing](#) the centralized protection mode.
- The **General Settings** item in the menu corresponds to the [settings](#) of the Dr.Web ConfigD component, which is responsible for the overall functioning of Dr.Web Industrial for UNIX File Servers.

If a component has sections with additional settings apart from the section with its main settings, then an icon indicating that you can expand/collapse additional sections is displayed to the left of the component name. If the icon looks like ►, additional sections are hidden. If the icon looks like ▼, additional sections are displayed on the menu, one per line. To expand/collapse the list of additional sections, click this expand/collapse icon next to the name of the required component.

- The additional sections with settings are displayed as indented lines. To view or edit parameters of an additional section, click its name.
- To add an additional subordinate section with settings for a component, if it is allowed, click + to the right of the component's name. Then, specify a unique name (tag) for the new subsection and click **OK**. To close the window without creating a subsection, click **Cancel**.
- To delete a subsection for a component, click ✖ to the right of the subsection name (tag) that appears when you hover over the component name. Then, confirm that you want to delete the subsection and click **Yes** or close the window without deleting the subsection by clicking **No**.

At the top of the settings page, you can see a menu that allows you to change the viewing mode. The following modes are available:

- **All**—show the table with all the component configuration parameters that can be viewed and adjusted.
- **Changed**—show the table with the component configuration parameters that have values different from the default ones.
- **Ini Editor**—show a text editor with this component configuration parameters that have values different from the default ones. The displayed text has the same format as the [configuration file](#) (contains `parameter = value` pairs).

You can also filter displayed parameters based on a search query. To filter unnecessary parameters out and display only those that correspond to the query, use the search box. The box is displayed on the right side of the viewing mode menu and is marked with 🔍. To filter the parameter list, enter any word in the search box. All parameters that do not have the entered word in their description, will be hidden (this filtering is not case-sensitive). To clear the search results and display the unfiltered list, click ✖ in the search box or erase the word in it.

Parameters can be filtered out only when they are displayed in tabular form (i.e. in the **All** and **Changed** viewing modes).



## Viewing and Editing Component Settings in Tabular Form

When viewing parameters in tabular form (the **All** and **Changed** viewing modes), each table row contains the name and description of the parameter (on the left) and its current value (on the right). For Boolean parameters (those that have only two available values: “Yes” and “No”), a check box is displayed instead of a value (checked means “Yes”, unchecked means “No”).



When you select to view all parameters (not only those that were changed), the modified (non-default) values are indicated in bold.

The complete parameter list is split into groups (such as **General**, **Advanced**, and so on). To collapse or expand a group, click on its heading (its name). When a group is collapsed and its parameters are not displayed in the table, the following icon appears to the left of the group name: ➤. When a group is expanded and the parameters are displayed in the table, the following icon appears to the left of the group name: ▼.


To adjust a parameter, click its current value in the table (for a Boolean parameter—set or remove a check mark in the corresponding check box). If a parameter has a set of predefined values, they will all appear as a drop-down list after you click the current value. If a parameter has a numeric value, an editing box will appear after you click the current value. Specify a required value and press ENTER. The figure below shows examples of how to change parameter values (note that the set of components shown in the figure can differ from the one supplied to you). All changes made to parameter values are immediately applied to the configuration of the corresponding component.

**Figure 3. Component settings in tabular form**

If the parameter expects a string as its value or accepts a list of arbitrary values, a pop-up window will appear once you click on the parameter current value to edit it. If the parameter accepts a list of values, they will be shown in a multi-line editing box (one value per line) as



shown in the figure below. To edit the listed values, you need to change, delete or add any required lines in the editing box.




**Figure 4. Editing a list of values**

After editing the value of a parameter **Save** to apply your changes and to close the window. To close the window without applying the changes click **Cancel** or click the **X** icon in the upper right corner of the pop-up window.

## Viewing and Editing Components' Settings in a Text Editor

When viewing [parameters](#) in the **Ini Editor** mode, they are displayed in the same format as in the [configuration file](#) of the product (as `parameter = value` pairs), where parameter is a parameter's name that is written directly into the configuration file (into the settings section of the corresponding component). In this mode, only those parameters are displayed whose values differ from the default ones (that is, parameters whose values are emphasized in bold font in the **All** viewing mode). The figure below shows how parameters are displayed in this simple-view text editor.



**Figure 5. Built-in editor for settings**

To make any desired changes, edit the text in this text editor according to the same rules as described for editing the configuration file (this will modify only the section that contains the settings of the component highlighted on the left). If necessary, you can specify a new value for any parameter available for the component. In this case, the value of this parameter changes from its default setting to the value you enter in the editor. If you want to reset the parameter back to its default value, just erase the line containing this parameter in this text editor. If you do so, then, once you save the changes, the parameter will be restored to its default value.

Once you have finished editing parameter values, click **Save** to apply the changes or click **Cancel** to cancel them.



If you click **Save**, the text is validated: the program checks whether all parameters are existent and their set values are valid. In case of an error, the appropriate message will be displayed.

For details on the configuration file, its, and its features that are important for specifying parameter values, refer to [Appendix D. Dr.Web Industrial for UNIX File Servers Configuration File](#) section.

## Additional Information

- [Configuration parameters](#) of Dr.Web ConfigD (Common settings).
- [Configuration parameters](#) of SpIDer Guard.
- [Configuration parameters](#) of Dr.Web ES Agent.
- [Configuration parameters](#) of Dr.Web Updater.
- [Configuration parameters](#) of Dr.Web File Checker.
- [Configuration parameters](#) of Dr.Web Scanning Engine.
- [Configuration parameters](#) of Dr.Web Network Checker.



- [Configuration parameters](#) of Dr.Web SNMPD.
- [Configuration parameters](#) of Dr.Web StatD.
- [Managing the Centralized Protection](#).

## Managing the Centralized Protection

You can connect Dr.Web Industrial for UNIX File Servers to the centralized protection server or switch back to the standalone mode, thereby disconnecting the product from the centralized protection server. To open the page where you can manage centralized protection, chose the item called **Centralized protection** from the settings menu on the **Settings** page.

To connect Dr.Web Industrial for UNIX File Servers to the centralized protection server or to disconnect from it, use the corresponding check box on this page.

### Connection to the Centralized Protection Server

At an attempt to connect to the centralized protection server a pop-up window will appear on the screen; in this window you need to specify the parameters for connecting to the centralized protection server.

The screenshot shows a dialog box titled "Set manually" with a close button (X) in the top right corner. Inside the dialog, there is a section labeled "Server address and port:" followed by a text input field. Below this is a section labeled "Server public key file:" with a text input field and a "Browse..." button. A collapsed section titled "Authentication (optional)" is shown below. It contains a "Workstation ID:" label with a text input field, and a "Password:" label with a text input field. At the bottom of this section is a checkbox labeled "Connect the workstation as 'newbie'". At the very bottom of the dialog are two buttons: "Connect" (highlighted in green) and "Cancel".

**Figure 6. Connection to the centralized protection server**

In the drop-down list located at the top of the window chose one of the methods for connecting to the centralized protection server. Three methods are available:

- *Load from file*
- *Set manually*



- *Detect automatically*

If you select the *Load from file* option, then in the corresponding field of this window you will also need to specify a path to a file that contains connection settings. The file is provided by the anti-virus network administrator. If you select the *Set manually* option, you will need to specify the address and the port of the centralized protection server. For the *Set manually* or *Detect automatically* options, you can also specify the path to the file containing the server public key (provided by your network administrator or internet service provider).

Additionally, in the **Authentication (optional)** section you can specify your workstation identifier and password for authentication on the centralized protection server if you know them. If these fields are filled in, then your connection to the centralized protection server will succeed only if a correct identifier/password pair was entered. If you leave these fields empty, connection to the centralized protection server is established only if it is approved by the centralized protection server (either automatically or by the anti-virus network administrator, depending on the server settings).

Moreover, you can use the **Connect the workstation as "newbie"** option (to connect as a new user). In this case, if the Newbie mode is allowed on the centralized protection server for connections from workstations, then the centralized protection server, after approving this connection, automatically generates a unique identifier/password pair, which will be from this time on used for connecting your computer to the server. Note that in this mode the centralized protection server generates a new account for your workstation even if your workstation already has another account on the server.



Connection parameters must be specified in strict accordance with the instructions provided by the administrator of your anti-virus network or service provider.

To connect to the server, specify all of the parameters, click **Connect** and wait for connection to be established. To close the window without establishing a server connection, click **Cancel**.



Once you have connected Dr.Web Industrial for UNIX File Servers to the centralized protection server, its operation will be managed by the centralized protection server, until you switch back to the standalone mode. Connection to the centralized protection server will be established automatically every time when Dr.Web Industrial for UNIX File Servers is started.

## Scanning Local Files

The web interface provides a capability to scan any files stored on your local computer (from which you are currently accessing the web interface) to determine whether the files have any malicious content, the scanning is done with the help of the scan engine that is part of Dr.Web Industrial for UNIX File Servers. The files selected for scanning will be uploaded (via the HTTP protocol) to your server on which Dr.Web Industrial for UNIX File Servers is running, but after the scanning, even if any threats are found, the files will not be stored on the server, neither will



they be moved to quarantine there. The user who sent the files to scan them will only be informed about the result of the scanning.



This function is available only if the Dr.Web Industrial for UNIX File Servers distribution includes the Dr.Web Network Checker component.

## Opening a Panel to Scan Local Files and Setting Parameters for the Scanning

You can select and upload the files that you want to scan via the scanning panel for local files which is displayed when you choose the **Scan File** item in the main menu of the web interface. The launched panel is displayed in the bottom right corner of the web interface. The figure below shows what the scanning panel for local files looks like.





Figure 7. The scanning panel for local files

To close this panel, click **X** on the panel top right-hand corner. By clicking the  icon you can display the settings for the scanning of local files: the maximum time to scan a file (which does not include the time it takes to upload the file to your server from your local computer), using the heuristic analysis during the scan, and also the maximum compression ratio for compressed objects and the maximum nesting level for objects packed into containers (such as archives).





Figure 8. Setting the parameters for the scanning of local files



To apply the changed settings and to return to the file selection mode where you can choose the files to scan, press the **Apply** button. To go back to file selection without applying your changes to the settings, press the **Cancel** button.


## Launching the Scanning of Local Files

To select files for scanning and to start their scanning, left-click on the target area that says **Drag files for scan here or click to select**. Upon your click there, a standard file selection window of your operation system file manager will open. You can choose multiple files at once for scanning. Please, note that you are not allowed to choose directories for scanning. You can also drag selected files with your mouse directly onto the target area of the file scanning panel from the file manager window. Once the files to be scanned have been specified, they will start being uploaded to your server where Dr.Web Industrial for UNIX File Servers is installed; and once a file is uploaded, its scanning starts. During the uploading and scanning of the files the file scanning panel displays the overall progress of the scanning procedure.



**Figure 9. Current progress for the scanning of local files**


If necessary, you can abort the scanning by pressing the **Stop** button. Once the scanning is completed, a report about the scanning of the uploaded files will be displayed on the file scanning panel.



**Figure 10. Results for the scanned local files**

If multiple files were uploaded, an extended report about the scanning will be available. To see the extended report, click the link that says **View report for all files**.





**Figure 11. Extended report about the scanned local files**

To close the report and to return to the state where the panel allows selecting new files for scanning, press **OK**.



It is possible to start scanning local files (using the current settings for the scanning) even when the file scanning panel is closed. To start uploading and scanning local files, just drag and drop them from the file manager window onto a page of the web interface opened in your browser.



## SplDer Guard



This component is included only in the distributions for GNU/Linux OS.

The Linux file system monitor SplDer Guard is designed for monitoring file activity on GNU/Linux file system volumes. The component operates as a resident monitor and controls main file system events related to modification (file creation, opening, closing). When such event is intercepted, the monitor checks whether the file was modified and, if so, the module generates a task for the [Dr.Web File Checker](#) file scanning component to scan the modified file by the [Dr.Web Scanning Engine](#) scan engine.

Moreover, the file system monitor SplDer Guard detects attempts to run programs from their executables files. If a program in an executable file is detected malicious during scanning, all processes started from this executable file will be forcibly terminated.

## Operating Principles

In this section:

- [General Information](#).
- [Defining Areas of the File System to be Monitored](#).
- [Enhanced File Monitoring Mode](#).

### General Information

The file system monitor SplDer Guard operates in user space (*user mode*) using fanotify mechanism. It is recommended that you use the *automatic mode* (`Auto`), which will allow the component to define the best operation mode on startup, as not all Linux kernel versions support fanotify used by the monitor. If the component cannot support the specified integration mode, the components exits after startup. If the auto mode is selected, the component attempts to use the fanotify mode. If this mode cannot be used, the component exits.

Once new or modified files are detected, the monitor sends to the [Dr.Web File Checker](#) file checker component a task to scan these files. The component then initiates their scanning by the [Dr.Web Scanning Engine](#) scan engine. The operation scheme is shown in the picture below. When operating via the fanotify system mechanism, the monitor can block access to files (of all types of files or only executable files—PE, ELF, scripts with a preamble #!) which are not scanned yet until they are fully scanned (see [below](#)).



The file system monitor SplDer Guard automatically detects mounting and demounting of new file system volumes (for example, on USB flash drives, CD/DVD, RAID arrays, and so on) and adjusts the list of monitored objects, if required.

## Defining Areas of the File System to be Monitored

To optimize the check of the file system, SplDer Guard controls requests only to those files that are in the file system scopes specified in the configuration. Each scope is defined as a path to some directory of the file system tree and is named as a *protected space*. A collection of all protected spaces forms a single *monitoring scope* controlled by the monitor. In addition, you can specify a collection of directories needed to be excluded from monitoring in the component settings (*exclusion scope*). If you did not specify any protected spaces in the component settings, the monitoring scope controls all the file system tree. This implies that those files are monitored if they belong to the monitoring scope and do not belong to the exclusion scope.

Specifying exclusion can be useful when, for example, some files are frequently modified, which results in constant repeated scanning of these files and, thus, can increase system load. If it is known with certainty that frequent modification of files in a directory is not caused by a malicious program but is due to operation of a trusted program, you can add the path to this directory or these files to the list of exclusions. In this case, the file system monitor SplDer Guard stops responding to modification of these objects, even if they are within the monitoring scope. Moreover, you can add a program to the list of trusted programs (the `ExcludedProc` configuration parameter). In this case, file operations of this program will not cause scanning even if the modified or created files are monitored. Similarly, if necessary, you can disable monitoring and scanning of files located in the other file systems that are mounted to the local file system (for example, external file server directories mounted via CIFS). To specify file systems whose files should not be scanned, use the `ExcludedFilesystem` parameter.

Protected spaces, as parts of monitoring scopes with the specified scan parameters, are set in the component settings as named sections, whose names contain a unique identifier assigned to the protected space. Each section describing the protected space contains the `Path` parameter that defines the path to the file system storing the space directories (i.e. the file system tree fragment that is monitored within this space) and the `ExcludedPath` parameter that defines a local (with respect to `Path`) exclusion scope inside the protected space. Note that the `ExcludedPath` parameter can contain standard file masks (i.e. the '\*' and '?' characters). You can also specify a global exclusion scope, using the `ExcludedPath` parameter specified outside the sections describing protected spaces. All catalogs belonging to this scope, including the directories of protected spaces, will be excluded from monitoring. Each protected space can be appended only with a global and its own exclusion scope: if one space is nested to another, the exclusion settings, specified for the enclosing space, are not applied to the nested space. In addition, each protected scope settings has the logical parameter `Enable` which determines whether the file monitoring is enabled or not. If this parameter is set to `No`, or the `Path` parameter has an empty value, the space contents is not monitored.



If all protected spaces specified in the monitor settings are not monitored or their paths are not specified, SplDer Guard is running idle because none of the files of the system file tree are monitored. If you want to monitor the file system as a single protected space, remove named space sections from the settings.

Consider an example of setting the monitor and exclusion scopes. Suppose the following parameters are set in the component settings:

```
[LinuxSpider]
ExcludedPath = /directory1/tmp
...

[LinuxSpider.Space.space1]
Path = /directory1
ExcludedPath = "*.tmp"
...

[LinuxSpider.Space.space2]
Path = /directory1/directory2
...

[LinuxSpider.Space.space3]
Path = /directory3
Enable = No
...
```

It means that files located in the `/directory1` directory and its subdirectories, except the `/directory1/tmp` folder, are monitored. Files whose full names match the mask `/directory1/*.tmp` are also not monitored (except the nested scope `/directory1/directory2` to which this mask is not applied despite the fact that the scope is nested in the protected space *space1*). Files in the `/directory3` directory are not monitored.

## Enhanced File Monitoring Mode

SplDer Guard can use three monitoring modes:

- *Regular* (set by default)—SplDer Guard monitors file access (creation, opening, closing, and running) and requests the file scanning. If a threat is detected upon the scan, an action is applied to neutralize the threat. Apps are allowed to access the file until the file scanning is finished.
- *Enhanced control of executable files*—SplDer Guard monitors files considered as non-executable like in the regular mode. Access to files that are considered as executable is blocked at the access attempt until the file scanning is finished.



Executable files are binary files of formats PE and ELF as well as text script files containing the `"#!"` preamble.



- “Paranoid” mode—SpIDer Guard blocks access to a file at any access attempt until the file scanning is finished.

Dr.Web File Checker stores scan results in cash during the specified period of time, so when an app access the file which scan results are in cash, the file will not be rescanned, the cached scan result will be used instead. Despite that, the “paranoid” mode significantly slows down access to files.

To configure monitoring mode change the `BlockBeforeScan` parameter value in the component [settings](#).



See the [File System Monitoring Setting](#) section for more information about configuring SpIDer Guard, as well as file monitoring modes.

## Command-Line Arguments

To run SpIDer Guard, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-spider [<parameters>]
```

SpIDer Guard can process the following options:

Parameter	Description
<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> <code>-h</code> <b>Arguments:</b> None.
<code>--version</code>	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> <code>-v</code> <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-spider --help
```

This command outputs short help information on SpIDer Guard.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon at the startup of the operating system. To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based



management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-spider`

## Configuration Parameters

The component uses the configuration parameters specified in the `[LinuxSpider]` section of the unified [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

- [Component Parameters](#).
- [Customizing Protected Space Individual Monitoring Settings](#).

## Component Parameters

The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<a href="#">Logging level</a> of the component.  If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.  Default value: <code>Notice</code>
<code>Log</code> <i>{log type}</i>	<a href="#">Logging method</a> of the component.  Default value: <code>Auto</code>
<code>ExePath</code> <i>{path to file}</i>	Component executable path.  Default value: <code>&lt;opt_dir&gt;/bin/drweb-spider</code> . <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-spider</code></li></ul>
<code>Start</code> <i>{logical}</i>	The component must be started by the <a href="#">Dr.Web ConfigD</a> configuration daemon.  Setting this parameter to <code>Yes</code> instructs the configuration daemon to start the component immediately; and setting this parameter to <code>No</code> instructs the configuration daemon to terminate the component immediately.  Default value: <i>Depends on the Dr.Web product in which the component is supplied and operates.</i>
<code>Mode</code> <i>{FANOTIFY   AUTO}</i>	Defines the SpIDer Guard operation mode.



Parameter	Description
	<p>Allowed values:</p> <ul style="list-style-type: none"><li>• FANOTIFY—use the <i>fanotify</i> monitoring interface;</li><li>• AUTO—select an optimal operation mode automatically.</li></ul> <p>Default value: AUTO</p>
<code>DebugAccess</code> <i>{logical}</i>	<p>Log or do not log detailed information on access attempts to files at the debug level (when <code>LogLevel = DEBUG</code>).</p> <p>Default value: No</p>
<code>ExcludedProc</code> <i>{path to file}</i>	<p>List of processes that are excluded from file monitoring. If a file operation was initiated by one of the processes specified in the parameter value, the modified or created file will not be scanned.</p> <p>Multiple values can be specified as a list. List values must be comma-separated and put in quotation marks. The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add the <code>wget</code> and <code>curl</code> processes to the list.</p> <ol style="list-style-type: none"><li>1. Adding values to the configuration file.<ul style="list-style-type: none"><li>• Two values per string:<pre>[LinuxSpider] ExcludedProc = "/usr/bin/wget", "/usr/bin/curl"</pre></li><li>• Two strings (one value per string):<pre>[LinuxSpider] ExcludedProc = /usr/bin/wget ExcludedProc = /usr/bin/curl</pre></li></ul></li><li>2. Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:<pre># drweb-ctl cfset LinuxSpider.ExcludedProc - a /usr/bin/wget # drweb-ctl cfset LinuxSpider.ExcludedProc - a /usr/bin/curl</pre></li></ol> <p>Default value: <i>(not specified)</i></p>
<code>ExcludedFilesystem</code> <i>{file system name}</i>	<p>Exclude the specified file system from monitoring.</p> <p>This option is available only in the FANOTIFY mode.</p> <p>Multiple values can be specified as a list. List values must be comma-separated and put in quotation marks. The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p>



Parameter	Description
	<p>Example: Add the <code>cifs</code> and <code>nfs</code> file systems to the list.</p> <ol style="list-style-type: none"><li>Adding values to the configuration file.<ul style="list-style-type: none"><li>Two values per string:<pre>[LinuxSpider] ExcludedFilesystem = "cifs", "nfs"</pre></li><li>Two strings (one value per string):<pre>[LinuxSpider] ExcludedFilesystem = cifs ExcludedFilesystem = nfs</pre></li></ul></li><li>Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:<pre># drweb-ctl cfset LinuxSpider.ExcludedFilesystem -a cifs # drweb-ctl cfset LinuxSpider.ExcludedFilesystem -a nfs</pre></li></ol> <p>Default value: <code>cifs</code></p>
<code>BlockBeforeScan</code> <i>{Off   Executables   All}</i>	<p>Block files until they are scanned by the monitor (in the enhanced or “paranoid” monitoring mode).</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li><code>Off</code>—do not block access to files even if they were not scanned;</li><li><code>Executables</code>—block access to executable files (PE, ELF files and scripts that contain the <code>#!</code> preamble) not scanned by the monitor;</li><li><code>All</code>—block access to any files not scanned by the monitor.</li></ul> <p>Files are blocked only in the <code>FANOTIFY</code> mode.</p> <p>Default value: <code>Off</code></p>
<code>[*] ExcludedPath</code> <i>{path to file or directory}</i>	<p>A path to an object (file or directory) to be excluded from file monitoring. Either a directory or a certain file can be specified. If a directory is specified, all files and subdirectories (including nested ones) will be skipped. You can use file masks (containing characters <code>?</code> and <code>*</code>, as well as symbol classes <code>[ ]</code>, <code>[! ]</code>, <code>[^ ]</code>).</p> <p>Multiple values can be specified as a list. List values must be comma-separated and put in quotation marks. The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add the <code>/etc/file1</code> file and the <code>/usr/bin</code> directory to the list.</p> <ol style="list-style-type: none"><li>Adding values to the configuration file.</li></ol>





Parameter	Description
	<ul style="list-style-type: none"><li>Two values per string: <pre>[LinuxSpider] ExcludedPath = "/etc/file1", "/usr/bin"</pre></li><li>Two strings (one value per string): <pre>[LinuxSpider] ExcludedPath = /etc/file1 ExcludedPath = /usr/bin</pre></li></ul> <p>2. Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset LinuxSpider.ExcludedPath - a /etc/file1 # drweb-ctl cfset LinuxSpider.ExcludedPath - a /usr/bin</pre> <p>Note that symbolic links here have no effect as only a direct path to a file is analyzed when scanning.</p> <p>Default value: <code>/proc, /sys</code></p>
<code>[*] OnKnownVirus</code> <code>{action}</code>	Action to be applied upon detection of a known threat (a virus and so on) in the scanned file.  Allowed values: Report, Cure, Quarantine, Delete.  Default value: Report
<code>[*] OnIncurable</code> <code>{action}</code>	Action to be applied upon detection of an incurable threat.  Allowed values: Quarantine, Delete.  Default value: Quarantine
<code>[*] OnSuspicious</code> <code>{action}</code>	Action to be applied upon detection of an unknown threat (or a suspicious object) in the scanned file by using heuristic analysis.  Allowed values: Report, Quarantine, Delete.  Default value: Report
<code>[*] OnAdware</code> <code>{action}</code>	Action to be applied upon detection of adware in the scanned file.  Allowed values: Report, Quarantine, Delete.  Default value: Report
<code>[*] OnDialers</code> <code>{action}</code>	Action to be applied upon detection of a dialer in the scanned file.  Allowed values: Report, Quarantine, Delete.  Default value: Report



Parameter	Description
[*] OnJokes {action}	Action to be applied upon detection of a joke program in the scanned file.  Allowed values: Report, Quarantine, Delete.  Default value: Report
[*] OnRiskware {action}	Action to be applied upon detection of riskware in the scanned file.  Allowed values: Report, Quarantine, Delete.  Default value: Report
[*] OnHacktools {action}	Action to be applied upon detection of a hacktool in the scanned file.  Allowed values: Report, Quarantine, Delete.  Default value: Report
[*] ScanTimeout {time interval}	Timeout for scanning one file.  Allowed values: from 1 second (1s) to 1 hour (1h).  Default value: 30s
[*] HeuristicAnalysis {On   Off}	Enable or disable the heuristic analysis for detection of unknown threats. The heuristic analysis provides higher detection reliability but increases the duration of scanning.  Action applied to threats detected by the heuristic analyzer is specified as the OnSuspicious parameter value.  Allowed values: <ul style="list-style-type: none"><li>• On—enable the heuristic analysis while scanning;</li><li>• Off—disable the heuristic analysis.</li></ul> Default value: On
[*] PackerMaxLevel {integer}	Maximum nesting level for packed objects. A packed object is executable code compressed with special software (UPX, PELock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects and so on. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects are not scanned.  The nesting level is not limited. If the value is set to 0, nested objects are not scanned.  Default value: 8
[*] ArchiveMaxLevel {integer}	Maximum nesting level for archives (.zip, .rar, and so on) in which other archives may be enclosed (and these archives may also include other archives, and so on). The value of this parameter specifies the



Parameter	Description
	<p>nesting limit beyond which archives enclosed in other archives are not scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 0</p>
<code>[*] MailMaxLevel</code> <code>{integer}</code>	<p>Maximum nesting level for files of mailers (.pst, .tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects are not scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 0</p>
<code>[*] ContainerMaxLevel</code> <code>{integer}</code>	<p>Maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, .jar files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 8</p>
<code>[*] MaxCompressionRatio</code> <code>{integer}</code>	<p>Maximum compression ratio of scanned objects (a ratio of an uncompressed size to a compressed size). If the ratio of an object exceeds the limit, this object is skipped while scanning.</p> <p>The compression ratio must be no less than 2.</p> <p>Default value: 500</p>

## Customizing Protected Space Individual Monitoring Settings

For each protected space of the file system, a separate section containing the path to the monitored file system area and the monitoring parameters is specified in the configuration file, together with the `[LinuxSpider]` section, which stores all the monitor parameters. Each section must be named as `[LinuxSpider.Space.<space name>]`, where *<space name>* is a unique identifier of the protected space.

The space individual section must contain the following parameters absent in the `[LinuxSpider]` general section:

Parameter	Description
Enable	The contents of the protected space located at <code>Path</code> (see below) must be monitored.



<i>{logical}</i>	To stop monitoring the contents of this protected space, set the parameter to <code>No</code> . Default value: <code>Yes</code>
<code>Path</code> <i>{path to directory}</i>	Path to the system directory with files) to be monitored (including nested directories).  By default, this parameter has an empty value—therefore, you should specify a value when adding a protected space to the monitoring scope.  Default value: <i>(not specified)</i>



If all protected spaces specified in the monitor settings are not monitored or their paths are not specified, SplDer Guard is running idle because none of the files of the system file tree are monitored. If you want to monitor the file system as a single protected space, remove all named space sections from the settings.

Except for those mentioned above, separate sections of protected spaces can include a list of parameters from the general section of the component settings that are marked with the “`[*]`” character in the table above and re-determine a parameter for this protected space (for example, a reaction on threat detection, the maximum archive check level, and so on). If a parameter is not specified for a protected space, the monitoring procedure for this space is adjusted with the corresponding parameter values taken from the `[LinuxSpider]` section.

To add a new section of parameters for the protected space with the `<space name>` tag using the [Dr.Web Ctl](#) management tool (started with the `drweb-ctl` command), run the command:

```
# drweb-ctl cfset LinuxSpider.Space -a <space name>
```

Example:

```
# drweb-ctl cfset LinuxSpider.Space -a Space1
# drweb-ctl cfset LinuxSpider.Space.Space1.Path /home/user1
```

The first command adds the `[LinuxSpider.Space.Space1]` section to the configuration file; the second one sets a value of the `Path` parameter for the section, specifying a path to the monitored file system area. Other parameters of this section will be the same as in the `[LinuxSpider]` general section.



## SplDer Guard for SMB

SplDer Guard for SMB is a monitor of shared file system directories used by SMB file server Samba. This component is designed to monitor actions applied to files in Samba shared directories. It operates as a resident monitor and controls basic actions in the protected file system (creation, opening, closing, and read or write operations). Once the component intercepts such operation, it checks whether the file was modified and if so, a task to scan the file is created and sent to the [Dr.Web File Checker](#) file scanner. If the file requires scanning, Dr.Web File Checker initiates the scanning by the [Dr.Web Scanning Engine](#) scan engine. If the file contains a threat, it is blocked for access for a period specified in settings until the threat is neutralized. Also the component settings can indicate file blocking in case of a scanning error (including cases when there is no valid license).



To avoid conflicts between SplDer Guard and SplDer Guard for SMB, which can occur in the process of scanning the files located in the shared directories of Samba, it is recommended that you additionally [configure](#) SplDer Guard by performing one of the following actions:

- Add Samba shared directories to the exclusion scope (specify these directories in the `ExcludedPath` parameter).
- Add the Samba process (`smbd`) to the list of ignored processes (specify `smbd` in the `ExcludedProc` parameter).



The SplDer Guard for SMB monitor uses a special VFS SMB module for the integration with the Samba server. With SplDer Guard for SMB, several versions of this module are supplied. They are built for various versions of Samba. However, the supplied versions of the VFS SMB module may be incompatible with the version of Samba installed on your file server. It may occur, for example, if your Samba server uses the `CLUSTER_SUPPORT` option.

If VFS SMB modules are incompatible with the Samba server, build the VFS SMB module for your Samba server from the supplied source codes manually (including the compatibility with the `CLUSTER_SUPPORT` option if necessary). The procedure of building the VFS SMB module from the supplied source code files is described in the [Building the VFS SMB Module](#) section.

## Operating Principles

In this section:

- [General Information](#).
- [Defining Areas of the File System to be Monitored](#).



## General Information

SpIDer Guard for SMB monitor operates in daemon mode (usually it is started by the [Dr.Web ConfigD](#) configuration daemon on system startup). After the startup, the component operates as a server to which special plug-ins are connected (VFS SMB modules) that operate on the Samba server side and monitors user activity in shared directories. Once new or modified files are found on a volume, the monitor instructs the [Dr.Web File Checker](#) file checker to scan the file.

If a file scanned at request of the monitor is infected with an incurable threat or with a threat for which the “Block” (*Block*) action is specified, the monitor instructs the VFS SMB module controlling the corresponding shared directory to block this file (that is, to prevent users from reading, editing, and running the file). A text file is also created next to the blocked object, if this setting is not disabled. The created text file describes the reason why the object was block. It is necessary to avoid the “unexpected disappearance” of the file to which the [action](#) “Delete” (*Delete*) or “Quarantine” (*Quarantine*) was applied. Thus, it prevents users from multiple attempts to recreate the moved or deleted file. Moreover, this text file also notifies the user that the computer may be infected with a malicious program. If informed on this, the user can start anti-virus scanning of the computer and neutralize local detected threats. Additionally file (depending on the value of the corresponding configuration parameter) can be blocked upon the scanning error, including the case when there is no valid license, which provides operation of SpIDer Guard for SMB.

## Defining Areas of the File System to be Monitored

You can disable monitoring of the specified files and directories stored in controlled shared directories of the Samba server. It can be useful when, for example, some files are frequently modified, which results in constant repeated scanning of these files and, thus, can increase system load. If it is known with certainty that frequent modification is typical for these files in the file server storage, it is recommended that you add them to the list of exclusions. In this case, the monitor stops responding to modification of these objects and their scanning is not initiated.

To distinguish between directories that are to be monitored and the exclusions, the file storage monitor for Samba—SpIDer Guard for SMB—uses two configuration parameters:

- `IncludedPath`—paths to be monitored (monitoring scope).
- `ExcludedPath`—paths to be excluded from monitoring (exclusion scope).

Normally, as the monitoring scope, the monitor uses the entire shared directory. If you specify different monitoring and exclusion scopes, only those files in shared directory are monitored whose paths are not specified in the `ExcludedPath` parameter or are specified in the `IncludedPath` parameter. If a path is specified in both parameters, the `IncludedPath` parameter has higher priority than the other one: the objects in the included path will be monitored by the Samba shared directories monitor—SpIDer Guard for SMB. Thus, use the



`IncludedPath` parameter to add some files and directories for monitoring if they are located in the exclusion scope.

You can specify different protection parameters for different Samba shared directories monitored by SpIDer Guard for SMB, including different monitoring and exclusion scope as well as reaction to detected threats. For that purpose, in the configuration section of SpIDer Guard for SMB, specify individual settings for VFS SMB modules that control shared directories.



See the [Integration with Samba File Server](#) section for information about integrating Dr.Web Industrial for UNIX File Servers with a file service.

## Command-Line Arguments

To launch SpIDer Guard for SMB from the command line of the operating system, the following command is used:

```
$ <opt_dir>/bin/drweb-smbspider-daemon [<parameters>]
```

SpIDer Guard for SMB can process the following options:

Parameter	Description
<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> <code>-h</code> <b>Arguments:</b> None.
<code>--version</code>	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> <code>-v</code> <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-smbspider-daemon --help
```

This command outputs short help information on SpIDer Guard for SMB.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon at the startup of the operating system. To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based



management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-smb spider-daemon`

## Configuration Parameters

### In this section

- [Component Parameters](#)
- [Customizing Monitoring Settings](#)

The component uses configuration parameters specified in the `[SMBSpider]` section of the unified [Appendix D. Dr.Web Industrial for UNIX File Servers Configuration File](#) of Dr.Web Industrial for UNIX File Servers.

## Component Parameters

The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<a href="#">Logging level</a> of the component.  If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.  Default value: <code>Notice</code>
<code>Log</code> <i>{log type}</i>	<a href="#">Logging method</a> of the component.  Default value: <code>Auto</code>
<code>ExePath</code> <i>{path to file}</i>	Component executable path.  Default value: <code>&lt;opt_dir&gt;/bin/drweb-smb spider-daemon</code> . <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-smb spider-daemon</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-smb spider-daemon</code></li></ul>
<code>Start</code> <i>{logical}</i>	The component must be started by the <a href="#">Dr.Web ConfigD</a> configuration daemon.  Setting the value of this parameter to <code>Yes</code> instructs the configuration daemon to start the component immediately, and setting the value of this parameter to <code>No</code> —to terminate the component immediately.  Default value: <code>No</code>





Parameter	Description
<code>SambaChrootDir</code> <i>{path to directory}</i>	<p>Path to the root directory of the SMB file storage (can be redefined by the file server with the help of the <code>chroot</code> restriction).</p> <p>Used as a prefix inserted at the beginning of all paths to files and directories residing in the file server storage and describes the path relative to the root of the local file system.</p> <p>If not specified, the <code>/</code> path to the file system root is used.</p> <p>Default value: <i>(not specified)</i></p>
<code>SmbSocketPath</code> <i>{path to file}</i>	<p>Path to the socket file which enables interaction between SpIDer Guard for SMB and VFS SMB modules.</p> <p>The path is always relative and is a supplement for the path specified as the <code>SambaChrootDir</code> parameter value (if the <code>SambaChrootDir</code> parameter is empty, then the <code>/</code> path to the file system root is supplemented).</p> <p>Default value: <code>var/run/.com.drweb.smb_spider_vfs</code></p>
<code>ActionDelay</code> <i>{time interval}</i>	<p>Delay time between the moment when a threat is detected and the moment when SpIDer Guard for SMB applies the action specified for this threat type. The file is blocked during this time period.</p> <p>Default value: <code>24h</code></p>
<code>MaxCacheSize</code> <i>{size}</i>	<p>Size of cache used by VFS SMB modules to store information about scanned files in monitored SMB directories.</p> <p>If <code>0</code> is specified, the cache is not used.</p> <p>Default value: <code>10mb</code></p>
<code>[*] ExcludedPath</code> <i>{path to file or directory}</i>	<p>Path to the shared directory object which must be skipped during scanning together with all nested directories and files. You can specify a directory or file path. It is also possible to use file masks (which contain the characters <code>?</code> and <code>*</code>, as well as character classes <code>[ ]</code>, <code>[! ]</code>, and <code>[^ ]</code>).</p> <p>Accepts a list of values. The values in the list must be comma-separated (with each value put in quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: add the <code>/etc/file1</code> file and <code>/usr/bin</code> directory to the list.</p> <ol style="list-style-type: none"><li>1. Adding values to the configuration file.<ul style="list-style-type: none"><li>• Two values per string:</li></ul></li></ol> <pre>[SMBSpider] ExcludedPath = "/etc/file1", "/usr/bin"</pre>




Parameter	Description
	<ul style="list-style-type: none"><li>Two strings (one value per string): <pre>[SMBSpider] ExcludedPath = /etc/file1 ExcludedPath = /usr/bin</pre></li></ul> <p>2. Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset SMBSpider.ExcludedPath - a /etc/file1 # drweb-ctl cfset SMBSpider.ExcludedPath - a /usr/bin</pre> <p>If a directory is specified, all directory content will be skipped. Default value: <i>(not specified)</i></p>
<code>[*] IncludedPath</code> <i>{path to file or directory}</i>	<p>Path to the shared directory object, which must be scanned. You can specify a directory or file path. It is also possible to use file masks (that contain characters <code>?</code> and <code>*</code>, as well as character classes <code>[ ]</code>, <code>[! ]</code>, and <code>[^ ]</code>).</p> <p>Accepts a list of values. The values in the list must be comma-separated (with each value put in quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: add the <code>/etc/file1</code> file and <code>/usr/bin</code> directory to the list.</p> <p>1. Adding values to the configuration file.</p> <ul style="list-style-type: none"><li>Two values per string: <pre>[SMBSpider] IncludedPath = "/etc/file1", "/usr/bin"</pre></li><li>Two strings (one value per string): <pre>[SMBSpider] IncludedPath = /etc/file1 IncludedPath = /usr/bin</pre></li></ul> <p>2. Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset SMBSpider.IncludedPath - a /etc/file1 # drweb-ctl cfset SMBSpider.IncludedPath - a /usr/bin</pre> <p>If a directory is specified, all directory contents including nested files and directories will be scanned.</p>



Parameter	Description
	<p>Note that this parameter has higher priority than the <code>ExcludedPath</code> parameter (see above); that is, if the same object (a file or directory) is specified in both parameter values, this object will be scanned.</p> <p>Default value: <i>(not specified)</i></p>
<code>[*] AlertFiles</code> <i>{logical}</i>	<p>Create or do not create a text file with the explanation of the reason for blocking for each blocked object. The created file will be named as <i>&lt;name of the blocked file&gt;.drweb.alert.txt</i>.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <b>Yes</b>—create files describing the reasons why the object was blocked;</li><li>• <b>No</b>—do not create files.</li></ul> <p>Default value: <b>Yes</b></p>
<code>[*] OnKnownVirus</code> <i>{action}</i>	<p>Action to be applied on detection of a known threat.</p> <p>Allowed values: <b>Report</b>, <b>Block</b>, <b>Cure</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Report</b></p>
<code>[*] OnIncurable</code> <i>{action}</i>	<p>Action to be applied on detection of an incurable threat.</p> <p>Allowed values: <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Quarantine</b></p>
<code>[*] OnSuspicious</code> <i>{action}</i>	<p>Action to be applied on detection of a suspicious object.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Report</b></p>
<code>[*] OnAdware</code> <i>{action}</i>	<p>Action to be applied upon detection of adware.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Pass</b></p>
<code>[*] OnDialers</code> <i>{action}</i>	<p>Action to be applied upon detection of a dialer.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Pass</b></p>
<code>[*] OnJokes</code> <i>{action}</i>	<p>Action to be applied upon detection of a joke program.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Pass</b></p>
<code>[*] OnRiskware</code> <i>{action}</i>	<p>Action to be applied upon detection of riskware.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p> <p>Default value: <b>Pass</b></p>
<code>[*] OnHacktools</code> <i>{action}</i>	<p>Action to be applied upon detection of a hacktool.</p> <p>Allowed values: <b>Pass</b>, <b>Report</b>, <b>Block</b>, <b>Quarantine</b>, <b>Delete</b>.</p>



Parameter	Description
	Default value: <code>Pass</code>
<code>[*] BlockOnError</code> <i>{logical}</i>	<p>Block or do not block access to a file if an attempt to scan it has failed or a license allowing to scan files with SpIDer Guard for SMB is absent.</p> <div> When there is no valid license, if this parameter is set to <code>Yes</code>, SpIDer Guard for SMB will block all files moved to the shared directory it protects.</div> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>Yes</code>—block access to the file;</li><li>• <code>No</code>—do not block.</li></ul> <p>Default value: <code>Yes</code></p>
<code>[*] ScanTimeout</code> <i>{time interval}</i>	<p>Timeout for scanning one file.</p> <p>Allowed values: from 1 second (<code>1s</code>) to 1 hour (<code>1h</code>).</p> <p>Default value: <code>30s</code></p>
<code>[*] HeuristicAnalysis</code> <i>{On   Off}</i>	<p>Enable or disable the heuristic analysis for detection of unknown threats. The heuristic analysis provides higher detection reliability but increases the duration of scanning.</p> <p>Action applied to threats detected by the heuristic analyzer is specified as the <code>OnSuspicious</code> parameter value.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>On</code>—enable the heuristic analysis while scanning;</li><li>• <code>Off</code>—disable the heuristic analysis.</li></ul> <p>Default value: <code>On</code></p>
<code>[*] PackerMaxLevel</code> <i>{integer}</i>	<p>Maximum nesting level for packed objects. A packed object is executable code compressed with special software (UPX, PElLock, PECompact, Petite, ASPack, Morphine and so on). Such objects may include other packed objects which may also include packed objects and so on. The value of this parameter specifies the nesting limit beyond which packed objects inside other packed objects are not scanned.</p> <p>All objects at a deeper nesting level are skipped during the scanning initiated by SpIDer Guard for SMB.</p> <p>The nesting level is not limited. If the value is set to <code>0</code>, nested objects are not scanned.</p> <p>Default value: <code>8</code></p>
<code>[*] ArchiveMaxLevel</code> <i>{integer}</i>	<p>Maximum nesting level for archives (<code>.zip</code>, <code>.rar</code>, and so on) in which other archives may be enclosed (and these archives may also include</p>



Parameter	Description
	<p>other archives, and so on). The value of this parameter specifies the nesting limit beyond which archives enclosed in other archives are not scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 0</p>
<code>[*] MailMaxLevel</code> <code>{integer}</code>	<p>Maximum nesting level for files of mailers (.pst, .tbb and so on) in which other files may be enclosed (and these files may also include other files and so on). The value of this parameter specifies the nesting limit beyond which objects inside other objects are not scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 8</p>
<code>[*] ContainerMaxLevel</code> <code>{integer}</code>	<p>Maximum nesting level when scanning other types objects inside which other objects are enclosed (HTML pages, .jar files, etc.). The value of this parameter specifies the nesting limit beyond which objects inside other objects will not be scanned.</p> <p>The nesting level is not limited. If the value is set to 0, nested objects are not scanned.</p> <p>Default value: 8</p>
<code>[*] MaxCompressionRatio</code> <code>{integer}</code>	<p>Maximum compression ratio of scanned objects (ratio between the compressed size and uncompressed size). If the ratio of an object exceeds the limit, this object is skipped during the scanning initiated by SpIDer Guard for SMB.</p> <p>The compression ratio must be no less than 2.</p> <p>Default value: 500</p>

## Customizing Monitoring Settings

You can specify a different tag for each VFS SMB module which monitors each shared directory (file storage). You can do that in the configuration file of the Samba SMB server (typically, this is the `smb.conf` file). Unique tags for VFS SMB modules in the `smb.conf` file are specified as follows:

```
smb_spider:tag = <name>
```

where `<name>` is a unique tag assigned to a VFS SMB module, which controls some shared directory, by the Samba server.



If a VFS SMB module has a unique tag `<name>`, you can create a separate section in the configuration file of Dr.Web Industrial for UNIX File Servers in addition to the `[SMBSpider]` section storing all SMB parameters. The created section will cover only parameters for scanning a particular file storage protected by the VFS SMB module to which the tag was assigned. This section should be named as follows: `[SMBSpider.Share.<name>]`.

Individual sections for VFS SMB modules can contain parameters indicated with the character `[*]` in the table above. Other parameters cannot be specified in individual sections because these parameters are defined simultaneously for all VFS SMB modules operating with SMB directory monitor Spider Guard for SMB.

A VFS SMB module using an individual section `[SMBSpider.Share.<name>]` gets the values of all parameters not provided in this section from the general section `[SMBSpider]`. Thus, if there are no tagged individual sections, all VFS SMB modules will use the same parameters for protection of shared directories being monitored. If you delete some parameter from the `[SMBSpider.Share.<name>]` section, the parameter value for this section (and for the corresponding shared directory with the `<name>` tag) will be inherited from the corresponding "parent" parameter with the same name from the general `[SMBSpider]` section rather than from the default parameter.

To add a new section for the shared Samba directory with the `<name>` tag using the [Dr.Web Ctl](#) command-line tool for Dr.Web Industrial for UNIX File Servers management (run with the `drweb-ctl` command), use the following command:

```
# drweb-ctl cfset SmbSpider.Share -a <name>
```

Example:

```
# drweb-ctl cfset SmbSpider.Share -a AccountingFiles
# drweb-ctl cfset SmbSpider.Share.AccountingFiles.OnAdware Quarantine
```

The first command adds the `[SMBSpider.Share.AccountingFiles]` section to the configuration file, and the second command changes the `OnAdware` parameter value in this section. Thus, the added section will contain all parameters marked with the `[*]` character in the table above, moreover, the values of all parameters except for the `OnAdware` parameter specified in the command will coincide with the parameter values from the `[SMBSpider]` general section.

## Building the VFS SMB Module

In this section:

- [General Information.](#)
- [Building the VFS SMB Module.](#)



## General Information

If it is detected during the Dr.Web Industrial for UNIX File Servers installation that the Samba version used on your file server is incompatible with all supplied versions of the VFS SMB modules for SpIDer Guard for SMB, you need to build the VFS SMB module manually using the supplied source codes.

The source codes of the VFS SMB module for SpIDer Guard for SMB are supplied in the additional package named `drweb-smbspider-modules-src` and are packed in the `tar.gz` archive. The `drweb-smbspider-modules-src` package contains a `drweb-smbspider-11.1.src.tar.gz` archive with the source codes. This archive is placed into `/usr/src/` directory. If the archive is absent in this directory, install the package with the source codes manually (from [repository](#) or [by custom installation](#) from the universal package, depending on the [way](#), of the Dr.Web Industrial for UNIX File Servers installation).

Beside the source codes of the VFS SMB module used by SpIDer Guard for SMB, you will also need the source codes of the Samba version installed on your file server. If you do not have the source codes, download them from the developer's source, for example <https://www.samba.org/samba/download/>. To determine which Samba version is installed on your file server, use the following command:

```
$ smbld -V
```



To build the VFS SMB module for SpIDer Guard for SMB, the source codes of the actual version of Samba installed on your server must be used. Otherwise, correct operation of the SpIDer Guard for SMB is not guaranteed.

To build the module manually from the source codes, administrative (root) privileges are required. For that purpose, you can use the `su` command to switch to another user or the `sudo` command to build the module as a different user.

## Building the VFS SMB Module

1. Unpack the archive with the VFS SMB module source codes to any directory. For example, the following command

```
# tar -xf drweb-smbspider-11.1.src.tar.gz
```

unpacks the source codes to the created directory. This directory has the archive name and is created in the same location where the archive resides.

2. Determine the version of Samba installed on your server and download its source codes if necessary.
3. Determine if the version of Samba installed on your server uses the `CLUSTER_SUPPORT` option. To do that, use the following command:



```
$ smbld -b | grep CLUSTER_SUPPORT
```

If the output contains the `CLUSTER_SUPPORT` string, the version of Samba installed on your server uses the `CLUSTER_SUPPORT` option.

4. Go to the directory with the Samba source codes, perform configuration (`./configure`) and then building (`make`) of the server. When configuring, define the correct value of the option responsible for `CLUSTER_SUPPORT`. To learn to configure and build Samba, refer to developer's official documentation, for example at <https://www.samba.org/samba/docs/>.



Note that building Samba from the source code files is necessary only for the correct building of the VFS SMB module used by SpIDer Guard for SMB in the next step. You do not have to replace Samba already installed on your server with the new binaries built from the source codes.

5. When you have successfully built Samba, go to the directory with the VFS SMB module source codes and issue the following command:

```
# ./configure --with-samba-source=<path to dir with Samba src> && make
```

where *<path to dir with Samba src>* is the path to the directory where Samba was built in the previous step.

6. When the VFS SMB module is successfully built, copy the `libsmb_spider.so` binary file from the `.libs` subdirectory (created while building) to the directory for the VFS modules of installed Samba (by default, for GNU/Linux, it is `/usr/lib/samba/vfs`) and rename it to `smb_spider.so`. To do that, use the following command:

```
# cp ../libs/libsmb_spider.so /usr/lib/samba/vfs/smb_spider.so
```

7. After copying of the built VFS SMB module, you can delete the directories where the VFS SMB module and the Samba server were built.

After that, it is necessary to complete integration between Dr.Web Industrial for UNIX File Servers and the Samba server the way it is described in the [corresponding](#) section in Administrator Manual. Please note that in this case, in the first step of the integration, it is not necessary to create the `smb_spider.so` symbolic link in the directory of the VFS modules of the installed Samba server.





## Dr.Web File Checker

The file scanning component Dr.Web File Checker is designed for scanning files and directories in the file system. It is used by other components of Dr.Web Industrial for UNIX File Servers to scan file system objects. Moreover, this component also functions as a quarantine manager, as it manages the contents of the directories where isolated files are kept.

## Operating Principles

This component is used to access any file system objects (files, directories, boot records). It is started with superuser (*root*) privileges.

It indexes all scanned files and directories and saves all the data about the objects that have been checked to a special cache to avoid repeated scanning of objects that have been already scanned and have not been modified since that (in this case, if a request to scan such an object is received, the previous scan result, retrieved from cache, is returned).

When requests to check file system objects are received from Dr.Web Industrial for UNIX File Servers components, it checks whether this object requires scanning. If so, a scanning task is generated for [Dr.Web Scanning Engine](#). If the scanned object contains a threat, Dr.Web File Checker puts it into detected threats registry and neutralizes it (cures, deletes or quarantines) if this action has been specified by the client component that initiated the scanning as the reaction to a threat. The scanning can be initiated by various components of the product (for example, by the [SplDer Guard for SMB](#) monitor).

During the scanning, the file-checking component generates and sends to the client component a report detailing the results of the scanning and the applied actions, if any.

Apart from the standard scanning method, the following special methods are available for internal use:

- *The “flow” scanning method.* A client component that uses this scanning method initializes detection and neutralization parameters only once. These parameters will be applied to all future requests to scan a file coming from this client component. This method is used by the [SplDer Guard](#) monitor.
- *The “proxy” scanning method.* When this method is used, the file-checking component scans files without applying any actions to detected threats and without keeping any records about the detected threats to permit future action. Any necessary actions must be applied by the component that initiated the scanning process. This method is used by the [SplDer Guard for SMB](#) monitor.

Files can be scanned with the “flow” scanning method using the `flowscan` command of the [Dr.Web Ctl](#) utility (launched with the `drweb-ctl` command). However, for a normal on-demand scanning, it is recommended that you use the `scan` command.



During its work, the file scanning component not only keeps a threats registry and manages quarantine, but also collects overall file scan statistics, averaging the number of files checked within a second in the last minute, last 5 minutes, last 15 minutes.

## Command-Line Arguments

To launch Dr.Web File Checker, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-filecheck [<parameters>]
```

Dr.Web File Checker can process the following parameters:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-filecheck --help
```

This command outputs short help information on Dr.Web File Checker.

## Startup Notes

The component cannot be launched directly from command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon when receiving requests on file system scanning from other components of Dr.Web Industrial for UNIX File Servers. To manage the operation of the component, as well as to scan files when needed, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is launched by using the `drweb-ctl` [command](#)).

To scan an arbitrary file or directory using Dr.Web File Checker you can use `scan` command of Dr.Web Ctl:

```
$ drweb-ctl scan <path to file or directory>
```



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-filecheck`.

## Configuration Parameters

The component uses configuration parameters which can be in the [FileCheck] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

This section stores the following parameters:

Parameter	Description
LogLevel <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the [Root] <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
Log <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
ExePath <i>{path to file}</i>	<p>Executable path to the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-filecheck</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-filecheck</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-filecheck</code></li></ul>
DebugClientIpc <i>{Boolean}</i>	<p>Indicates whether detailed IPC messages should be included into the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>).</p> <p>Default value: <code>No</code></p>
DebugScan <i>{Boolean}</i>	<p>Write detailed messages received during file scanning to the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>).</p> <p>Default value: <code>No</code></p>
DebugFlowScan <i>{Boolean}</i>	<p>Write detailed messages about file scanning by the “<i>flow</i>” method to the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>). Normally this scanning method is used by the <a href="#">SpIDer Guard</a> monitor.</p> <p>Default value: <code>No</code></p>
DebugProxyScan <i>{Boolean}</i>	<p>Write detailed messages about file scanning by the “<i>proxy</i>” method to the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>). Normally this scanning method is used by the <a href="#">SpIDer Guard for SMB</a> monitor.</p> <p>Default value: <code>No</code></p>



Parameter	Description
<code>DebugCache</code> <i>{Boolean}</i>	<p>Write detailed messages about the cached results of scanning should be included to the log file on the debug level (i.e. when <code>LogLevel = DEBUG</code>).</p> <p>Default value: <code>No</code></p>
<code>MaxCacheSize</code> <i>{size}</i>	<p>Maximum allowed size of cache to store data about scanned files.</p> <p>If <code>0</code> is specified, caching is disabled.</p> <p>Default value: <code>50mb</code></p>
<code>RescanInterval</code> <i>{time interval}</i>	<p>Period of time during which a file will not be rescanned if the results of its previous scan are available in the cache (the period during which the stored information is considered up-to-date).</p> <p>Acceptable values: from <code>0s</code> to <code>1m</code> inclusive. If the set interval is less than <code>1s</code>—there will be no delay, the file will be scanned upon any request.</p> <p>Default value: <code>1s</code></p>
<code>IdleTimeLimit</code> <i>{time interval}</i>	<p>Maximum idle time for the component. When the specified period of time expires, the component shuts down.</p> <p>Acceptable values: from <code>10s</code> to <code>30d</code> inclusive. If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the components goes idle.</p> <p>Default value: <code>30s</code></p>



## Dr.Web Network Checker

Network checker agent Dr.Web Network Checker is designed for scanning the data received through the network in the scan engine, as well as distributed file scanning for threats. The component allows to arrange a connection between network hosts with installed Dr.Web Industrial for UNIX File Servers for receiving and transmitting data (for example, file content) via the network hosts to perform its scanning. The component organizes automatic distribution of scanning tasks (by transmitting and receiving them over the network) to all available network hosts to which it is configured. The component balances the load between the hosts caused by scanning tasks. If there are no configured connections with remote hosts, the component transmits all the data to the local Dr.Web Scanning Engine only.

Note that the component is always used to scan the data received via network connections. Thus, if the component is missing or unavailable, the performance of the components that transmit data for scanning via the network connection will be incorrect.



This component is not designed to organize distributed scanning of files located in the local file system, since it cannot replace the Dr.Web File Checker component. To organize distributed scanning of local files, use [Dr.Web MeshD](#) component.

In case of high intensity of scanning of data transferred via the network, there is a possibility of having problems with scanning due to depletion of the number of available file descriptors. In this case, it is necessary to increase the limit of the number of file descriptors available to Dr.Web Industrial for UNIX File Servers.

During scanning, data can be shared either over an open channel or over a protected one, applying SSL/TLS. To use a secure HTTPS connection it is required to provide an appropriate SSL server certificate and private key for hosts that share files. To generate SSL keys and certificates, you can use the `openssl` utility. An example of how to use the `openssl` utility to generate a certificate and a private key is given in the section [Appendix E. Generating SSL certificates](#).

## Operating Principles

The component allows sending the data not represented as files in the local file system for scanning into [Dr.Web Scanning Engine](#) engine (located on local or remote host). This data is processed by the components which send data for scanning via network connection. Mind that these components always use Dr.Web Network Checker for files transmission to Dr.Web Scanning Engine engine, even if it is located on local host. Thus, if Dr.Web Network Checker is unavailable, *these components cannot work correctly*.

In addition, Dr.Web Network Checker allows the Dr.Web Industrial for UNIX File Servers connection with a given set of nodes on the network with the Dr.Web Industrial for UNIX File Servers installed on them (or any other Dr.Web for UNIX solution 10.1 or later) in order to organize distributed checks data presence which is not represented as files in the local file



system. Thereby, this component allows to create and configure a *scanning cluster*, which is a set of network nodes that exchange data for verification (each instance must have its own instance of the Dr.Web Network Checker distributed verification agent). On each node of the network included in the scanning cluster, Dr.Web Network Checker performs automatic distribution of tasks for scanning data, transferring it over the network to all available nodes with which the connection is configured. At the same time, the load balancing on nodes is performed, caused by data verification depending on the amount of resources available on remote nodes (as an indicator of the amount of resources available for load, the number of child scanning processes generated by the scanning core Dr.Web Scanning Engine on this node is used). The lengths of the files queues waiting for checking on each used node are also estimated.

In this case, any network node included in the scanning cluster can act as a scanning client that transmits data to a remote scan as well as a scanning server that receives data from the specified network nodes for verification. If necessary, the distributed scanning agent can be configured so that the node acts only as a scanning server or only as a scanning client.

The data received via network for scanning is saved to the local file system as temporary files and are sent to [Dr.Web Scanning Engine](#) engine or, in case if it is unavailable, to the other node of the scanning cluster.

The `InternalOnly` parameter, which you can find in [settings](#), allows to manage the Dr.Web Network Checker operation mode. It indicates if Dr.Web Network Checker is used for including Dr.Web Industrial for UNIX File Servers to the scanning cluster or for internal purposes of the Dr.Web Industrial for UNIX File Servers local components only.



You can create your own component (external application) which will use Dr.Web Network Checker to check the files (including distributing the scanning jobs to the nodes of the scanning cluster). For this, the Dr.Web Network Checker component provides a custom API based on the Google Protobuf technology. The Dr.Web Network Checker API, as well as client application sample code that uses Dr.Web Network Checker, are supplied as part of `drweb-netcheck` package.

The example of creating the scanning cluster can be found in [Creating the Scanning Cluster](#) section.

## Command-Line Arguments

To run Dr.Web Network Checker, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-netcheck [<parameters>]
```

Dr.Web Network Checker can process the following options:

Parameter	Description
-----------	-------------



<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> <code>-h</code> <b>Arguments:</b> None.
<code>--version</code>	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> <code>-v</code> <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-netcheck --help
```

This command outputs short help information on Dr.Web Network Checker.

## Startup Notes

The component cannot be run directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is run automatically by the configuration daemon [Dr.Web ConfigD](#) configuration daemon when required (usually on operating system startup). If, in the component [configuration](#), a value of the `FixedSocket` parameter is specified and the `InternalOnly` parameter is set to `No`, the agent is always running and available for clients via the specified UNIX socket. To start scanning via network, you can use the [Dr.Web Ctl](#) command-line tool for Dr.Web Industrial for UNIX File Servers management (it is started with the `drweb-ctl` [command](#)). If there are no configured connections to remote hosts, the local scanning will be started.

To scan an arbitrary file or directory using Dr.Web Network Checker you can use `netscan` command of Dr.Web Ctl tool:

```
$ drweb-ctl netscan <path to file or directory>
```



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-netcheck`.

## Configuration Parameters

The component uses configuration parameters which can be found in the `[NetCheck]` section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.



The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
<code>Log</code> <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
<code>ExePath</code> <i>{path to file}</i>	<p>Executable path to the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-netcheck</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-netcheck</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-netcheck</code></li></ul>
<code>FixedSocket</code> <i>{path to file   address}</i>	<p>Socket of the fixed Dr.Web Network Checker agent instance.</p> <p>If this parameter is specified, the <a href="#">Dr.Web ConfigD</a> configuration daemon checks that there is always a running component copy of the distributed scanning agent that is available to the clients via this socket.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>&lt;path to file&gt;</code> is a path to a local UNIX socket;</li><li>• <code>&lt;address&gt;</code> is a network socket as a pair <code>&lt;IP address&gt;:&lt;port&gt;</code>.</li></ul> <p>Default value: <i>(not set)</i></p>
<code>InternalOnly</code> <i>{Boolean}</i>	<p>Managing the operation mode of the component.</p> <p>If the value is set to <code>Yes</code>, the component is used for internal purposes of the Dr.Web Industrial for UNIX File Servers components only and it is not used for including Dr.Web Industrial for UNIX File Servers to the scanning cluster and for processing external (to the Dr.Web Industrial for UNIX File Servers) client applications, regardless of the <code>LoadBalance*</code> settings and the value of the <code>FixedSocket</code> parameter.</p> <p>Default value: <code>No</code></p>
<code>RunAsUser</code> <i>{UID   user name}</i>	<p>The name of the user on whose behalf the component is run. The user name can be specified either as the user's number UID or as the user's login. If the user name consists of numbers (i.e. similar to number UID), it is specified with the "name:" prefix, for example: <code>RunAsUser = name:123456</code>.</p>





Parameter	Description
	<p>When a user name is not specified, the component operation terminates with an error after the startup.</p> <p>Default value: <code>drweb</code></p>
<code>IdleTimeLimit</code> <i>{time interval}</i>	<p>Maximum idle time for the component. If the specified value is exceeded, the component shuts down.</p> <p>If the <code>LoadBalanceAllowFrom</code> or <code>FixedSocket</code> parameter is set, this setting is ignored (the component does not finish its operation after the time interval expires).</p> <p>Acceptable values: from 10 seconds (10s) to 30 days (30d) inclusive.</p> <p>If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the components goes idle.</p> <p>Default value: <code>30s</code></p>
<code>LoadBalanceUseSsl</code> <i>{Boolean}</i>	<p>Use SSL/TLS for connecting to other hosts.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>Yes</code>—use SSL/TLS;</li><li>• <code>No</code>—do not use SSL/TLS.</li></ul> <p>If the parameter is set to <code>Yes</code>, a certificate and the corresponding private key should be specified for this host and for hosts with which it interacts (the parameters <code>LoadBalanceSslCertificate</code> and <code>LoadBalanceSslKey</code>).</p> <p>Default value: <code>No</code></p>
<code>LoadBalanceSslCertificate</code> <i>{path to file}</i>	<p>Path to the SSL certificate used by Dr.Web Network Checker for communication with other hosts via a secure SSL/TLS connection.</p> <p>Please note that the certificate file and the private key file (which is specified by a parameter described below) must form a matching pair.</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceSslKey</code> <i>{path to file}</i>	<p>Path to the private key used by Dr.Web Network Checker for communication with other hosts via a secure SSL/TLS connection.</p> <p>Please note that the certificate file and the private key file (which is specified by the mentioned parameter) must form a matching pair.</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceSslCa</code> <i>{path}</i>	<p>The path to the directory or file with the list of trusted root certificates. Among these certificates, there must be a certificate that certifies the authenticity of the certificates used by agents</p>



Parameter	Description
	<p>within the scanning cluster when exchanging data over SSL/TLS protocols.</p> <p>If the parameter value is empty, Dr.Web Network Checker working on this host does not authenticate certificates of interacting agents; however, depending on the settings, these agents can authenticate the certificate used by the agent operating on the host.</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceSslCrl</code> <i>{path}</i>	<p>Path to the directory or file with system list of revoked certificates.</p> <p>If the parameter value is not specified, Dr.Web Network Checker running on this host does not check the certificates of the interacting agents for validity, but they may check the validity of the certificate used by the agent running on this host, depending on the settings.</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceServerSocket</code> <i>{address}</i>	<p>Network socket (IP address and port) which is listened on this host by Dr.Web Network Checker for receiving files sent by remote hosts for scanning (if it can operate as a scanning server).</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceAllowFrom</code> <i>{IP address}</i>	<p>IP address of a remote network host from which the Dr.Web Network Checker receives files for scanning (as a scanning server).s</p> <p>You can specify a list as the parameter value. The values in the list must be separated with commas (each value in the quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add to the list of host addresses 192.168.0.1 and 10.20.30.45.</p> <ol style="list-style-type: none"><li>Adding of values to the configuration file.<ul style="list-style-type: none"><li>Two values in a line:<pre>[NetCheck] LoadBalanceAllowFrom = "192.168.0.1", "10.20.30.45"</pre></li><li>Two lines (a value per line):<pre>[NetCheck] LoadBalanceAllowFrom = 192.168.0.1 LoadBalanceAllowFrom = 10.20.30.45</pre></li></ul></li></ol>



Parameter	Description
	<p>2. Adding values via the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset NetCheck.LoadBalanceAllowFrom -a 192.168.0.1 # drweb-ctl cfset NetCheck.LoadBalanceAllowFrom -a 10.20.30.45</pre> <p>If the parameter is empty, removed files cannot be received for scanning (the host does not operate as a scanning server).</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceSourceAddress</code> <i>{IP address}</i>	<p>IP address of a network interface used by Dr.Web Network Checker on the host for transferring files for their remote scanning (if the host operates as a scanning server and has several network interfaces).</p> <p>If an empty value is specified, the network interface automatically selected by the OS kernel is used.</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceTo</code> <i>{address}</i>	<p>Socket (IP address or port) of a remote host to which Dr.Web Network Checker on the host can send files for their remote scanning (as a network scanning client).</p> <p>You can specify a list as the parameter value. The values in the list must be separated with commas (each value in the quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add sockets 192.168.0.1:1234 and 10.20.30.45:5678 to the list.</p> <p>1. Adding of values to the configuration file.</p> <ul style="list-style-type: none"><li>Two values in one string:</li></ul> <pre>[NetCheck] LoadBalanceTo = "192.168.0.1:1234",                "10.20.30.45:5678"</pre> <ul style="list-style-type: none"><li>Two strings (one value per a string):</li></ul> <pre>[NetCheck] LoadBalanceTo = 192.168.0.1:1234 LoadBalanceTo = 10.20.30.45:5678</pre> <p>2. Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset NetCheck.LoadBalanceTo -a 192.168.0.1:1234 # drweb-ctl cfset NetCheck.LoadBalanceTo -a 10.20.30.45:5678</pre>



Parameter	Description
	<p>If the parameter value is empty, local files cannot be transferred for a remote scanning (the host does not operate as a network scanning client).</p> <p>Default value: <i>(not set)</i></p>
<code>LoadBalanceStatusInterval</code> <i>{time interval}</i>	<p>Time interval considered by the host to send the next message containing information about its workload to all scanning clients (specified in the <code>LoadBalanceAllowFrom</code> parameter).</p> <p>Default value: <code>1s</code></p>
<code>SpoolDir</code> <i>{path to directory}</i>	<p>Local file system directory used to store files sent over the network for scanning and received by Dr.Web Network Checker.</p> <p>Default value: <code>/tmp/netcheck</code></p>
<code>LocalScanPreference</code> <i>{fractional number}</i>	<p>Relative weight (priority) of the host which is considered when a scanning server is selected to scan a file (a local file or a file received over the network). If the relative weight of the local station is greater than the weights of all hosts available as scanning servers, files are scanned locally.</p> <p>Minimum value: <code>1</code>.</p> <p>Default value: <code>1</code></p>

## Creating the Scanning Cluster

In this section:

- [Introductory Remarks.](#)
- [The Example of Creating the Scanning Cluster.](#)
- [Configuring Cluster Nodes.](#)
- [Verifying the Cluster Operability.](#)

### Introductory Remarks

To create the scanning cluster that allows to perform the distributed checks (while scanning files or other objects), you need to have a set of network nodes with the installed Dr.Web Network Checker component on each node. To make the cluster node not only to receive and transmit data to be scanned, it is also necessary to have the scan engine Dr.Web Scanning Engine installed on the node. Thus, to create the node of the scanning cluster, it is necessary that the minimum set of the following components is installed (minimally) on the server (other components of Dr.Web Industrial for UNIX File Servers which are installed automatically to ensure the functionality of the components listed here, are skipped):

1. Dr.Web Network Checker (`drweb-netcheck` package) is a component that provides networking between nodes;




2. **Dr.Web Scanning Engine** (`drweb-se` package) is the scan engine that is need for scanning data received via network. The component may be absent, in this is node will only transmit data to be checked to other scanning cluster nodes.

The nodes that constitute the scanning cluster form *peer to peer* network, i.e. each of the nodes, depending on which **settings** are defined in the Dr.Web Network Checker component on this node, is able to act as either a *scanning client* (which transmits data for scanning to other nodes) or as a *scanning server* (which receives data for scanning from other nodes). With the appropriate settings, the cluster node can be both the scanning client and the scanning server at the same time.

The Dr.Web Network Checker parameters, related to scanning cluster setting, have names starting with `LoadBalance`.

## The Example of Creating the Scanning Cluster

Study the example of creating the scanning cluster, displayed on the figure below.



**Figure 12. The scanning cluster structure**

In this case, it is assumed that the cluster consists of three nodes (displayed on the figure as *node 1*, *node 2*, and *node 3*). In this case, node 1 and node 2 are servers with a full-fledged Dr.Web product for UNIX servers installed (for example, Dr.Web for UNIX file servers or Dr.Web for UNIX internet gateways, the product type does not matter), and node 3 is used only for assistance in scanning files transferred from nodes 1 and 2. Therefore, only the minimum required component set (Dr.Web Network Checker and Dr.Web Scanning Engine) is installed, other components that are automatically installed to ensure the node operability, such as Dr.Web ConfigD, are not displayed on the figure). Nodes 1 and 2 can work both as servers and scanning clients between each other (perform mutual distribution of the load, associated with scanning), and node 3—only as a server, receiving tasks from nodes 1 and 2.



These components will be distributed between the locally installed scan engine Dr.Web Scanning Engine and the cluster partner nodes, acting as scanning servers depending on the load balance.



It is important to note that only components scan data that is not represented as files in the local file system, can act as a client module of verification. This means that the scanning cluster cannot be used for distributed scanning of files by SplDer Guard file system monitors and by the Dr.Web File Checker component.

## Configuring Cluster Nodes

To customize the specified cluster configuration you need to change Dr.Web Network Checker settings on all cluster nodes. All following settings are given as `.ini` file (refer to configuration file [format](#) description).

### Node 1

```
[NetCheck]
InternalOnly=No
LoadBalanceUseSsl = No
LoadBalanceServerSocket = <Node 1 IP address> : <Node 1 port>
LoadBalanceAllowFrom = <Node 2 IP address>
LoadBalanceSourceAddress = <Node 1 IP address>
LoadBalanceTo = <Node 2 IP address> : <Node 2 port>
LoadBalanceTo = <Node 3 IP address> : <Node 3 port>
```

### Node 2

```
[NetCheck]
InternalOnly=No
LoadBalanceUseSsl = No
LoadBalanceServerSocket = <Node 2 IP address> : <Node 2 port>
LoadBalanceAllowFrom = <Node 1 IP address>
LoadBalanceSourceAddress = <Node 2 IP address>
LoadBalanceTo = <Node 1 IP address> : <Node 1 port>
LoadBalanceTo = <Node 3 IP address> : <Node 3 port>
```

### Node 3

```
[NetCheck]
InternalOnly=No
LoadBalanceUseSsl = No
LoadBalanceServerSocket = <Node 3 IP address> : <Node 3 port>
LoadBalanceAllowFrom = <Node 1 IP address>
LoadBalanceAllowFrom = <Node 2 IP address>
```



Notes:

- Other (not mentioned here) Dr.Web Network Checker parameters are left unchanged.
- IP addresses and port numbers should be changed to real.
- Using of SSL for data exchange between nodes in this example is disabled. If you need to use SSL, you must set the value `Yes` for `LoadBalanceUseSsl` parameter, as well as set the needed values for the following parameters `LoadBalanceSslCertificate`, `LoadBalanceSslKey` and `LoadBalanceSslCa`.

## Verifying the Cluster Operability

To check the cluster operation in data distribution mode, use the following [command](#) on nodes 1 and 2:

```
$ drweb-ctl netscan <path to file or directory>
```

When executing the specified command, files from the specified directory should be checked by Dr.Web Network Checker, which should distribute the check to customized cluster nodes. To view statistics of network checks on each node before scanning, run the display of the statistics of Dr.Web Network Checker using the following [command](#) (to interrupt the displaying of statistics press CTRL+C):

```
$ drweb-ctl stat -n
```



## Dr.Web Scanning Engine

The Dr.Web Scanning Engine scan engine is designed to search for viruses and other malicious objects in files and boot records (*MBR—Master Boot Record, VBR—Volume Boot Record*) of disk devices. The component loads the scan engine Dr.Web Virus-Finding Engine into memory and starts it as well as loads Dr.Web virus databases used by the engine for threat detection.

The scan engine operates in the daemon mode, as a service which receives scanning requests from other Dr.Web Industrial for UNIX File Servers components (these are Dr.Web File Checker and Dr.Web Network Checker, and, partially, Dr.Web MeshD). If Dr.Web Scanning Engine and Dr.Web Virus-Finding Engine are absent or unavailable, no anti-virus scanning is performed on this node (except for Dr.Web Industrial for UNIX File Servers contains the Dr.Web MeshD component, which settings contain the connection to local cloud nodes, providing scan engine services).

## Operating Principles

The component operates as a service which receives requests to scan file system objects (files and boot disk records) from the Dr.Web Industrial for UNIX File Servers components on embedded threats. It also queues scanning tasks and scans requested objects by using the Dr.Web Virus-Finding Engine scan engine. If a threat is detected and it must be cured according to the scanning task, the scan engine attempts to cure it if this action can be applied to the scanned object.

The scanning engine, the Dr.Web Virus-Finding Engine scan engine, and the virus databases form one unit and cannot be separated: the scan engine downloads virus databases and provides the operation environment for the cross-platform scan engine Dr.Web Virus-Finding Engine. The virus databases and the scan engine are updated by the [Dr.Web Updater](#) update component that is included in Dr.Web Industrial for UNIX File Servers, but this component is not a part of the scan engine. The update component is run by the [Dr.Web ConfigD](#) configuration daemon periodically or forcefully, if the corresponding command is sent by the user. Moreover, if Dr.Web Industrial for UNIX File Servers operates in the centralized protection mode, updating of virus databases and the scan engine is performed by the [Dr.Web ES Agent](#). The latter component interacts with the centralized protection server and receives the updates.

The Dr.Web Scanning Engine can operate both under management of the configuration daemon Dr.Web ConfigD and in an autonomous mode. In the former case, the daemon runs the engine and ensures that anti-virus databases are up to date. In the latter case, the engine startup and the updating of virus databases is performed by an external application that uses the engine. The Dr.Web Industrial for UNIX File Servers components that issue requests to the scan engine asking it to scan files use the same interface as other external applications.





Users are provided with the opportunity to create own component (external application) using Dr.Web Scanning Engine for files checks. For this, Dr.Web Scanning Engine contains a special API, based on Google Protobuf. To obtain Dr.Web Scanning Engine API guide and examples of client application using Dr.Web Scanning Engine, contact Doctor Web partner care department (<https://partners.drweb.com/>).

Received tasks are automatically distributed into queues with different priorities: high, normal and low. Selection of the queue depends on the component that created a task: for example, tasks created by a file system monitor receive high priority as response time is important for monitoring. The scan engine computes statistics of its operations, including the number of all tasks received for scanning and the queue length. As the average load rate, the scan engine uses the average length of queues per second. This rate is averaged for the last minute, last 5 minutes and last 15 minutes.

The Dr.Web Virus-Finding Engine scan engine supports signature analysis (signature-based threat detection) and other [methods](#) of heuristic and behavioral analysis designed for detection of potentially dangerous objects based on machine instructions and other attributes of executable code.



Heuristic analysis cannot guarantee highly reliable results and may commit the following errors:

- *Errors of the first type.* These errors occur when a safe object is detected as malicious (false positive detections).
- *Errors of the second type.* These errors occur when a malicious object is detected as safe.

Thus, objects detected by the heuristics analyzer are treated as *Suspicious*.

It is recommended that you choose to move suspicious objects to quarantine. After virus databases are updated, such files can be scanned using signature analysis. Keep the virus databases up to date in order to avoid errors of the second type.

The Dr.Web Virus-Finding Engine scan engine allows to scan and cure both files and packed objects or objects in different containers (such as archives, email messages, and so on).

## Command-Line Arguments

To run the scan engine Dr.Web Scanning Engine from the command line, type the following command:

```
$ <opt_dir>/bin/drweb-se <socket> [<parameters>]
```

where the mandatory *<socket>* argument indicates the address of the socket used by Dr.Web Scanning Engine for processing requests of the client components. It can be set only as a file path (UNIX socket).



Dr.Web Scanning Engine can process the following options:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.
<i>Additional launch parameters (they are the same as configuration file parameters and substitute them when required):</i>	
--CoreEnginePath	<b>Function:</b> Specify the path to the library of the Dr.Web Virus-Finding Engine scan engine. <b>Short form:</b> No. <b>Arguments:</b> <path to the file>—a full path to the library that you want to use.
--VirusBaseDir	<b>Function:</b> Specify the path to the directory with virus database files. <b>Short form:</b> No. <b>Arguments:</b> <path to the directory>—path to the virus database directory.
--TempDir	<b>Function:</b> Specify the path to the directory with temporary files. <b>Short form:</b> No. <b>Arguments:</b> <path to the directory>—full path to the directory with temporary files.
--Key	<b>Function:</b> Specify the path to the key file. <b>Short form:</b> No. <b>Arguments:</b> <path to the file>—a full path to the key file that you want to use.
--MaxForks	<b>Function:</b> Specify the maximum allowed number of child processes which can be started by Dr.Web Scanning Engine during scanning. <b>Short form:</b> No. <b>Arguments:</b> <number>—the maximum allowed number of child processes.
--WatchdogInterval	<b>Description:</b> Frequency with which Dr.Web Scanning Engine checks whether child processes are operable and stops those processes that stopped responding. <b>Short form:</b> No. <b>Arguments:</b> <time interval>—frequency of checking child processes.
--Shelltrace	<b>Function:</b> Turn on the shell tracing (log detailed information on file scanning performed by Dr.Web Virus-Finding Engine). <b>Short form:</b> No. <b>Arguments:</b> None.



<code>--LogLevel</code>	<p><b>Description:</b> Set the level of logging executed by Dr.Web Scanning Engine during the operation.</p> <p><b>Short form:</b> No.</p> <p><b>Arguments:</b> <i>&lt;logging level&gt;</i>. Allowed values:</p> <ul style="list-style-type: none"><li>• <code>DEBUG</code>—the most detailed logging level. All messages and debug information are registered.</li><li>• <code>INFO</code>—all messages are registered.</li><li>• <code>NOTICE</code>—all error messages, warnings, and notifications are registered.</li><li>• <code>WARNING</code>—all error messages and warnings are registered.</li><li>• <code>ERROR</code>—only error messages are registered.</li></ul>
<code>--Log</code>	<p><b>Description:</b> Specify the method for logging component messages.</p> <p><b>Short form:</b> No.</p> <p><b>Arguments:</b> <i>&lt;log type&gt;</i>. Allowed values:</p> <ul style="list-style-type: none"><li>• <code>Stderr[:ShowTimestamp]</code>—messages are output to a standard error stream <i>stderr</i>. The additional option <code>ShowTimestamp</code> is used to add a time stamp to every message.</li><li>• <code>Syslog[:&lt;facility&gt;]</code>—messages are transmitted to the system logging service <code>syslog</code>. Additional option <i>&lt;facility&gt;</i> is used to specify a level at which <code>syslog</code> registers messages. The following values are possible:<ul style="list-style-type: none"><li>◦ <code>DAEMON</code>—messages of daemons.</li><li>◦ <code>USER</code>—messages of user processes.</li><li>◦ <code>MAIL</code>—messages of mail programs.</li><li>◦ <code>LOCAL0</code>—messages of local processes 0.</li><li>...</li><li>◦ <code>LOCAL7</code>—messages of local processes 7.</li></ul></li><li>• <i>&lt;path&gt;</i>—path to the file where all messages are registered.</li></ul> <p><b>Examples:</b></p> <pre>--Log /var/opt/drweb.com/log/se.log --Log Stderr:ShowTimestamp --Log Syslog:DAEMON</pre>

**Example:**

```
$ /opt/drweb.com/bin/drweb-se /tmp/drweb.ipc/.se --MaxForks=5
```

This command starts an instance of the Dr.Web Scanning Engine scan engine, creates the `/tmp/drweb.ipc/.se` UNIX socket for the interaction with the client components and limits the number of child scanning processes to 5.



## Startup Notes

When necessary, any number of instances of the Dr.Web Scanning Engine scan engine can be started. The instances provide the scanning service for client applications (not only for the Dr.Web Industrial for UNIX File Servers components). At that, if a value of the `FixedSocketPath` parameter is specified in the component [configuration](#), one instance of the scan engine is always running by the [Dr.Web ConfigD](#) configuration daemon and is always available for the clients via this UNIX socket. The instances of the scan engine started directly from the command line, will operate in an autonomous mode without establishing connection to the configuration daemon, even if it is running. To manage the operation of the component, as well as to scan files when needed, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is launched by using the `drweb-ctl` [command](#)).

To scan an arbitrary file or directory using Dr.Web Scanning Engine you can use `rawscan` command of Dr.Web Ctl tool:

```
$ drweb-ctl rawscan <path to file or directory>
```



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-se`.

## Configuration Parameters

The component uses configuration parameters which can be found in the `[ScanEngine]` section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

This section stores the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<a href="#">Logging level</a> of the component.  If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.  Default value: <code>Notice</code>
<code>Log</code> <i>{log type}</i>	<a href="#">Logging method</a> of the component.  Default value: <code>Auto</code>
<code>ExePath</code> <i>{path to file}</i>	Executable path to the component.  Default value: <code>&lt;opt_dir&gt;/bin/drweb-se</code> . <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-se</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-se</code></li></ul>



Parameter	Description
<code>FixedSocketPath</code> <i>{path to file}</i>	<p>Path to the UNIX socket of the fixed instance of the Dr.Web Scanning Engine scan engine.</p> <p>If this parameter is specified, the <a href="#">Dr.Web ConfigD</a> configuration daemon checks that there is always a running component copy of the scan engine that is available to the clients via this socket.</p> <p>Default value: <i>(not set)</i></p>
<code>IdleTimeLimit</code> <i>{time interval}</i>	<p>Maximum idle time for the component. When the specified period of time expires, the component shuts down.</p> <p>If the <code>FixedSocketPath</code> parameter is set, this setting is ignored (the component does not finish its operation after the time interval expires).</p> <p>Acceptable values: from 10 seconds (10s) to 30 days (30d) inclusive. If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the components goes idle.</p> <p>Default value: 1h</p>
<code>MaxForks</code> <i>{integer}</i>	<p>Maximum allowed number of child processes run by Dr.Web Scanning Engine, which can be run simultaneously.</p> <p>Default value: <i>Automatically determined</i> as twice the number of available CPU cores; or 4, if the resulting number is less than 4.</p>
<code>BufferedIo</code> <i>{On   Off}</i>	<p>Use buffered input/output (I/O) when scanning files.</p> <p>Using buffered I/O in the FreeBSD and GNU/Linux OSes can increase scanning speed of the files on slow disks.</p> <p>Default value: <code>Off</code></p>
<code>WatchdogInterval</code> <i>{time interval}</i>	<p>Rate at which Dr.Web Scanning Engine checks whether child processes are operable in order to detect processes that stopped responding ("watchdog").</p> <p>Default value: 1.5s</p>



## Dr.Web Updater

The update component Dr.Web Updater is designed for receiving all available updates for virus databases and the Dr.Web Virus-Finding Engine scan engine from Doctor Web update servers and synchronize updates with local cloud of Dr.Web for UNIX products (via the [Dr.Web MeshD](#), if it is present in the product) component.

If Dr.Web Industrial for UNIX File Servers operates in the [centralized protection mode](#), the updates are received from the centralized protection server (for example, from Dr.Web Enterprise Server); at that, all updates are received from the server via [Dr.Web ES Agent](#), and Dr.Web Updater is not used for downloading updates (updates synchronization with a local cloud of Dr.Web for UNIX products is not produced either).

## Operating Principles

The component is designed to establish connections to Doctor Web update servers to check for updates for virus databases and the Dr.Web Virus-Finding Engine scan engine. The lists of servers which constitute an available update zone are stored in a special file (the file is signed to prevent modification). Only basic and digest authentication are supported for connection to Doctor Web update servers.

If Dr.Web Industrial for UNIX File Servers is not connected to the centralized protection server or is connected to the server in the mobile mode, Dr.Web Updater is automatically started by the Dr.Web ConfigD configuration daemon. The startup is performed at periods specified in the [settings](#). The component can be also started by the configuration daemon if the appropriate [command](#) is received from a user (unscheduled update).

When updates become available on the servers, they are downloaded to the `<var_dir>/cache` directory (for GNU/Linux—`var/opt/drweb.com/cache`), after that they are moved to the working directories of Dr.Web Industrial for UNIX File Servers.

By default, all updates are performed from the updating zone which is common for all Dr.Web products. The list of the servers used by default, which are included to the updating zone, is specified in the files which are located in directories, defined in `*Dr1Dir` parameters, grouped by the update type: for virus databases and the scan engine, database of web resource categories (these files are grouped according to the component which is updated—virus databases and the scan engine, the anti-spam component). Upon user request the special update zone can be created (for each update type), the server list which is specified in separate file (named `custom.drl`, by default), located in directory specified in `*CustomDr1Dir` parameter. In this case, the update component will receive updates only from these servers, without using servers from the default zone.

If you do not want to use the special updating zone, clear the `*CustomDr1Dir` value of the corresponding parameter in the component settings.



The content of the files with server lists is signed, so that the files cannot be modified. If you need to create a special list of update servers, contact [technical support](#).

The component can back up the updated files for the next rollback of the updates, performed at user request. You can specify the location and the detail level of the backed up files in the settings. To roll back updates, use the command-line tool for Dr.Web Industrial for UNIX File Servers for managing the solution from the Dr.Web Ctl [Dr.Web Ctl](#) command line (it is run by `drweb-ctl` command).

If Dr.Web Industrial for UNIX File Servers is connected to the local cloud of Dr.Web for UNIX products, and it is not connected to the centralized protection server, the Dr.Web Updater component is used to synchronize updates received by cloud hosts as well, that is, it transmits updates received from update servers to the cloud, and receives updates from the cloud, which allows to reduce the total load on the Dr.Web update server. This option can be enabled or disabled in the component [settings](#).

## Command-Line Arguments

To run Dr.Web Updater, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-update [<parameters>]
```

Dr.Web Updater can process the following options:

Parameter	Description
<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> <code>-h</code> <b>Arguments:</b> None.
<code>--version</code>	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> <code>-v</code> <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-update --help
```

This command outputs short help information on Dr.Web Updater.



## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon when needed. To manage the operation of the component, as well as to update virus databases and the scan engine, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-update`.

## Configuration Parameters

The component uses configuration parameters which can be found in the [Update] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<a href="#">Logging level</a> of the component.  If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the [Root] <a href="#">section</a> is used.  Default value: <code>Notice</code>
<code>Log</code> <i>{log type}</i>	<a href="#">Logging method</a> of the component.  Default value: <code>Auto</code>
<code>ExePath</code> <i>{path to file}</i>	Executable path to the component.  Default value: <code>&lt;opt_dir&gt;/bin/drweb-update</code> . <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-update</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-update</code></li></ul>
<code>RunAsUser</code> <i>{UID   user name}</i>	The parameter determines under which user name the component should be run. The user name can be specified either as the user's number UID or as the user's login. If the user name consists of numbers (i.e. similar to number UID), it is specified with the "name:" prefix, for example: <code>RunAsUser = name:123456</code> .  When a user name is not specified, the component operation terminates with an error after the startup.  Default value: <code>drweb</code>





Parameter	Description
<code>UpdateInterval</code> <i>{time interval}</i>	<p>The frequency to check for updates on Dr.Web update servers. This is a time period between a previous successful attempt to connect to the update servers (initiated automatically or manually) and the next attempt to perform an update.</p> <p>Default value: 30m</p>
<code>RetryInterval</code> <i>{time interval}</i>	<p>Frequency of repeated attempts to perform an update using the update servers if the previous attempt failed.</p> <p>Acceptable values: from 1 minute (1m) to 30 minutes (30m) inclusive.</p> <p>Default value: 3m</p>
<code>MaxRetries</code> <i>{integer}</i>	<p>Number of repeated attempts to perform an update using the update servers (at the rate specified in <code>RetryInterval</code>) if the previous attempt failed.</p> <p>If the value is set to 0, repeated attempts are not made (the next update will be performed after the time period specified in <code>UpdateInterval</code>).</p> <p>Default value: 3</p>
<code>Proxy</code> <i>{connection string}</i>	<p>Stores the parameters for connecting to a proxy server that is used by the updater component (Dr.Web Updater) when it is connecting to Dr.Web updates servers (for example, if direct connections to external servers are prohibited by your network security policies).</p> <p>If the parameter value is not specified, the proxy server is not used.</p> <p>Allowed values:</p> <p><code>&lt;connection string&gt;</code> is the proxy server connection string. The string has the following format (URL):</p> <p><code>[ &lt;protocol&gt; : / / ] [ &lt;user&gt; : &lt;password&gt; @ ] &lt;host&gt; : &lt;port&gt;</code></p> <p>where:</p> <ul style="list-style-type: none"><li>• <code>&lt;protocol&gt;</code> is the utilized protocol type (in the current version, only <code>http</code> is available);</li><li>• <code>&lt;user&gt;</code> is the username to connect to the proxy server;</li><li>• <code>&lt;password&gt;</code> is the password to connect to the proxy server;</li><li>• <code>&lt;host&gt;</code> is the host address of the proxy (IP address or domain name, i.e. FQDN);</li><li>• <code>&lt;port&gt;</code> is the port to be used.</li></ul> <p>The parts URL <code>&lt;protocol&gt;</code> and <code>&lt;user&gt;:&lt;password&gt;</code> may be absent. The proxy server address <code>&lt;host&gt;:&lt;port&gt;</code> is mandatory.</p> <p>If the username or password contains the following characters: '@', '%' or ':', these characters must be changed to the following HEX codes: "%40", "%25" and "%3A", respectively.</p>



Parameter	Description
	<p>Examples:</p> <ol style="list-style-type: none"><li>In the configuration file:<ul style="list-style-type: none"><li>Connection to a the proxy server hosted at <i>proxyhost.company.org</i> using port 123: <code>Proxy = proxyhost.company.org:123</code></li><li>Connection to the proxy server hosted at <i>10.26.127.0</i> using port 3336 over HTTP protocol as user "legaluser" with the password "passw": <code>Proxy = http://legaluser:passw@10.26.127.0:3336</code></li><li>Connection to the proxy server hosted at <i>10.26.127.0</i>, using port 3336, username "user@company.com", password "passw%123": <code>Proxy = user%40company.com:passw%25123%3A@10.26.127.0:3336</code></li></ul></li><li>Setting the same values using the <code>drweb-ctl cfset</code> <a href="#">command</a>:<pre># drweb-ctl cfset Update.Proxy proxyhost.company.org:123 # drweb-ctl cfset Update.Proxy http://legaluser:passw@10.26.127.0:3336 # drweb-ctl cfset Update.Proxy user% 40company.com:passw%25123%3A@10.26.127.0:3336</pre></li></ol> <p>Default value: <i>(not set)</i></p>
<code>ExcludedFiles</code> <i>{file name}</i>	<p>Defines the name of the file that will not be updated by the Dr.Web Updater component.</p> <p>You can specify a list as the parameter value. The values in the list must be separated with commas (each value in the quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add to the list the following files: <code>123.vdb</code> and <code>456.dws</code>.</p> <ol style="list-style-type: none"><li>Adding of values to the configuration file.<ul style="list-style-type: none"><li>Two values in one string:<pre>[Update] ExcludedFiles = "123.vdb", "456.dws"</pre></li><li>Two strings (one value per a string):<pre>[Update] ExcludedFiles = 123.vdb ExcludedFiles = 456.dws</pre></li></ul></li></ol>



Parameter	Description
	<p>2. Adding values via the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset Update.ExcludedFiles -a 123.vdb # drweb-ctl cfset Update.ExcludedFiles -a 456.dws</pre> <p>Default value: <code>drweb32.lst</code></p>
<code>NetworkTimeout</code> <i>{time interval}</i>	<p>A time-out period imposed on the network-related operations of the updater component during the updating process.</p> <p>This parameter is used when a connection is temporarily lost: if the connection is established again before the time-out expires, the interrupted updating process will be continued.</p> <p>Specifying the time-out value larger than 75s has no effect as the connection is closed by TCP timeout.</p> <p>Minimum value: 5s.</p> <p>Default value: 60s</p>
<code>BaseDrlDir</code> <i>{path to directory}</i>	<p>Defines a path to directory that contains files used for connection to update servers of a standard update zone, which are used by the update component for updating virus databases and the scan engine.</p> <p>Default value: <code>&lt;var_dir&gt;/drl/bases</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/drl/bases</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/drl/bases</code></li></ul>
<code>BaseCustomDrlDir</code> <i>{path to directory}</i>	<p>Defines a path to directory that contains files used for connection to a special "customized" update zone, which are used by the for updating virus databases and the scan engine.</p> <p>If in the directory defined in parameter, is a non-empty signed server list file (<code>.drl</code> file), the update is performed only from these servers, and the main zone servers (see above) are not used to update the virus databases and the scan engine.</p> <p>Default value: <code>&lt;var_dir&gt;/custom-drl/bases</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/custom-drl/bases</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/custom-drl/bases</code></li></ul>
<code>BaseUpdateEnabled</code> <i>{Boolean}</i>	<p>Indicator that shows whether or not updating of virus databases and the scan engine is allowed.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• Yes—updating is allowed and will be performed;</li><li>• No—updating is not allowed and will not be performed.</li></ul> <p>Default value: Yes</p>



Parameter	Description
VersionDrlDir <i>{path to directory}</i>	<p>Defines a path to directory that contains files used for connection to servers, which are used for updating Dr.Web Industrial for UNIX File Servers versions.</p> <p>Default value: <code>&lt;var_dir&gt;/drl/version</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/drl/version</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/drl/version</code></li></ul>
VersionUpdateEnabled <i>{Boolean}</i>	<p>Indicator that shows whether or not updating of Dr.Web Industrial for UNIX File Servers component version is allowed.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• Yes—updating is allowed and will be performed;</li><li>• No—updating is not allowed and will not be performed.</li></ul> <p>Default value: Yes</p>
DwsCustomDrlPath <i>{path to file}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/drl/dws/custom.drl</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/drl/dws/custom.drl</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/drl/dws/custom.drl</code></li></ul>
DwsDrlDir <i>{path to directory}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/drl/dws</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/drl/dws</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/drl/dws</code></li></ul>
DwsCustomDrlDir <i>{path to directory}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/custom-drl/dws</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/custom-drl/dws</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/custom-drl/dws</code></li></ul>
DwsUpdateEnabled <i>{Boolean}</i>	<p>The parameter is not used.</p> <p>Default value: Yes</p>
AntispamDrlDir <i>{path to directory}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/drl/antispam</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/drl/antispam</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/drl/antispam</code></li></ul>
AntispamCustomDrlDir <i>{path to directory}</i>	<p>The parameter is not used.</p> <p>Default value: <code>&lt;var_dir&gt;/custom-drl/antispam</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/var/opt/drweb.com/custom-drl/antispam</code>.</li><li>• For FreeBSD: <code>/var/drweb.com/custom-drl/antispam</code></li></ul>



Parameter	Description
<code>AntispamUpdateEnabled</code> <i>{Boolean}</i>	The parameter is not used. Default value: <code>No</code>
<code>BackupDir</code> <i>{path to directory}</i>	Path to the directory, where the previous versions of updated files are saved for possible rollback. Upon every update only updated files are backed up. Default value: <code>/tmp/update-backup</code>
<code>MaxBackups</code> <i>{integer}</i>	The maximum number of the previous versions of updated files, which are saved. If this number is exceeded the oldest copy is removed upon the next update.  If the parameter value is zero, the previous versions of the files are not saved. Default value: <code>0</code>
<code>IdleTimeLimit</code> <i>{time interval}</i>	Maximum idle time for the component. When the specified period of time expires, the component shuts down.  The component is launched upon the next update by schedule or an explicit <code>drweb-ctl update [--local-cloud]</code> command. When the update is completed, it is waiting for the specified time interval, and if there are no new requests (including interaction with the cloud if <code>UseLocalCloud = Yes</code> ), then it shuts down until the next update attempt.  Acceptable values: from 10 seconds (10s) to 30 days (30d) inclusive. If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the components goes idle. Default value: <code>30s</code>
<code>UseLocalCloud</code> <i>{Boolean}</i>	Interact with a local cloud of Dr.Web for UNIX products via the <a href="#">Dr.Web MeshD</a> component for the update synchronization (send updates to the cloud, get updates from the cloud) in addition to the Dr.Web update servers.  Allowed values: <ul style="list-style-type: none"><li><code>No</code>—update using Dr.Web update servers only. Update synchronization with the cloud is disabled, but can be performed explicitly, by the <code>drweb-ctl update --local-cloud</code> command;</li><li><code>Yes</code>—update synchronization on the host with a local cloud (getting updates from the cloud if available, sending updates to the cloud, if the updates on the host are newer).</li></ul> Default value: <code>Yes</code>



## Dr.Web ES Agent

Central anti-virus protection agent Dr.Web ES Agent is designed for connecting Dr.Web Industrial for UNIX File Servers to the [centralized protection](#) server (for example, to Dr.Web Enterprise Server).

When Dr.Web Industrial for UNIX File Servers is connected to the centralized protection server Dr.Web ES Agent, the license [key file](#) are synchronized according to the key files stored on the centralized protection server. Moreover, Dr.Web ES Agent sends statistics on virus events, the list of running components and their status to the centralized protection server.

Dr.Web ES Agent also updates virus databases of Dr.Web Industrial for UNIX File Servers directly from the connected centralized protection server bypassing the update component [Dr.Web Updater](#).

## Operating Principles

Dr.Web ES Agent establishes connection to the centralized protection server (for example, to Dr.Web Enterprise Server), which allows the network administrator to implement common security policy within the network, in particular, configure the same scanning settings and reaction on threat detection for all network stations and servers. Moreover, the centralized protection server also performs a role of an internal update server on the network, as it stores up-to-date virus databases, (in this case, updating is performed via Dr.Web ES Agent, [Dr.Web Updater](#) is not used).

When connecting Dr.Web ES Agent to the centralized protection server, the agent ensures receipt of up-to-date settings for the program components and the license key file, which are then transmitted to the [Dr.Web ConfigD](#) configuration daemon for applying them to managed components. Moreover, the component also receives tasks to scan file system objects on the station (including scheduled tasks).

Dr.Web ES Agent collects and sends the server statistics on detected threats and applied actions.

To connect Dr.Web ES Agent to the centralized protection server, the password and identifier of the host ("station" in terms of the Centralized protection server) are required, as well as the public encryption key file, which is used by the server for authentication. Instead of the station identifier, you can specify the identifier of the main and tariff groups where the station is to be included. For required identifiers and public key file, contact the administrator of your anti-virus network.

Moreover, if this option is allowed on the centralized protection server, you can connect your host with the protected server ("workstation") as a "newbie". In this case, after the administrator confirms the request to connect, the centralized protection server automatically generates an identifier and a password, and sends them to the agent for future connections.



## Command-Line Arguments

To run Dr.Web ES Agent, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-esagent [<parameters>]
```

Dr.Web ES Agent can process the following options:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-esagent --help
```

This command outputs short help information on Dr.Web ES Agent.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon at the startup of the operating system. To manage the operation of the component, as well as to connect Dr.Web Industrial for UNIX File Servers to the centralized protection server, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-esagent`.

## Configuration Parameters

The component uses configuration parameters which can be found in the `[ESAgent]` section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.




The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
<code>Log</code> <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
<code>ExePath</code> <i>{path to file}</i>	<p>Executable path to the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-esagent</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-esagent</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-esagent</code></li></ul>
<code>DebugIpc</code> <i>{Boolean}</i>	<p>Write IPC messages to the debug log <code>LogLevel = DEBUG</code> (interaction of Dr.Web ES Agent and the <a href="#">Dr.Web ConfigD</a> configuration daemon).</p> <p>Default value: <code>No</code></p>
<code>MobileMode</code> <i>{On   Off   Auto}</i>	<p>Enable/disable the mobile mode when connected to a centralized protection server.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>On</code>— use the mobile mode if it is allowed by the centralized protection server (that is, perform updates from update servers of Doctor Web via <a href="#">Dr.Web Updater</a>);</li><li>• <code>Off</code>—do not use the mobile mode and continue operation in the centralized protection mode (updates are always received from the centralized protection server);</li><li>• <code>Auto</code>—use the mobile mode, if allowed by the centralized protection server, and perform updates both from update servers of Doctor Web via Dr.Web Updater and from the centralized protection server, depending on which connection is available and which connection quality is higher.</li></ul> <p>Note that behavior of this parameter depends on server permissions: if the mobile mode is not allowed on the server in use, this parameter has no effect.</p> <p>Default value: <code>Auto</code></p>
<code>Discovery</code> <i>{On   Off}</i>	<p>Enable/disable for the agent receiving <i>discovery</i> requests from the network inspector built in the centralized protection server (<i>discovery</i> requests are used by the inspector to check the structure and state of the anti-virus network).</p>





Parameter	Description
	<p>Allowed values:</p> <ul style="list-style-type: none"><li>• <code>On</code>—enable receiving and processing <i>discovery</i> requests;</li><li>• <code>Off</code>—disable receiving and processing <i>discovery</i> requests.</li></ul> <p>Note that this parameter has higher priority than settings of the centralized protection server: if the parameter value is set to <code>Off</code>, the agent does not receive discovery requests even if this option is enabled on the server.</p> <p>Default value: <code>On</code></p>
<code>UpdatePlatform</code> <i>{platform name}</i>	<p>Enable/disable for the agent receiving updates for the scan engine from the centralized protection server. The scan engine was developed for the indicated platform, where the <i>platform name</i> is a string, which contains the platform name.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• for GNU/Linux: <code>unix-linux-32</code>, <code>unix-linux-64</code>, <code>unix-linux-mips</code>;</li><li>• for FreeBSD: <code>unix-freebsd-32</code>, <code>unix-freebsd-64</code>;</li><li>• for Darwin: <code>unix-darwin-32</code>, <code>unix-darwin-64</code></li></ul> <div> It is strongly recommended to change the parameter value only if you are sure it is required.</div> <p>Default value: <i>Depends on the platform currently being used</i></p>
<code>SrvMsgAutoremove</code> <i>{integer}</i>	<p>The storage period after which the messages from the centralized protection server are removed automatically.</p> <p>Allowed values: from 1 week (<code>1w</code>) to 365 days (<code>365d</code>). The storage period is specified as an integer with a suffix (<code>s</code>, <code>m</code>, <code>h</code>, <code>d</code>, <code>w</code>).</p> <p>Default value: <code>1w</code></p>



## Dr.Web HTTPD

Dr.Web HTTPD provides infrastructure for local and remote interaction with Dr.Web Industrial for UNIX File Servers via HTTP (for example, via a web browser). The component provides an interface to manage Dr.Web Industrial for UNIX File Servers.

Besides managing Dr.Web Industrial for UNIX File Servers through the Dr.Web web interface, it is also possible to use the command interface (HTTP API) of Dr.Web HTTPD directly to interact with the components of Dr.Web Industrial for UNIX File Servers via HTTPS. This capability allows you to create your own interface to manage Dr.Web Industrial for UNIX File Servers.

For details about the HTTP API provided by Dr.Web HTTPD, refer to the [corresponding section](#).

To use a secure HTTPS connection, it is required to provide an appropriate SSL server certificate and private key for Dr.Web HTTPD. By default, an SSL server certificate and an SSL private key are generated for Dr.Web HTTPD automatically during the installation procedure, but, if necessary, you can generate your own certificate and key. Also, a user personal authorization certificate signed by a certificate authority certificate that is trusted by Dr.Web HTTPD can be used for automatic client authorization when connecting to Dr.Web HTTPD.

To generate SSL keys and certificates, you can use the `openssl` utility. An example of how to use the `openssl` utility to generate a certificate and a private key is given in the section [Appendix E. Generating SSL certificates](#).

## Operating Principles

Dr.Web HTTPD is a web server for managing the operation of Dr.Web Industrial for UNIX File Servers. With Dr.Web HTTPD, it is possible not to use external web servers (for example, Apache HTTP Server or Nginx) and management services like Webmin. Moreover, the component can function simultaneously with such servers and services on the same host without impeding their operation.

The Dr.Web HTTPD server processes requests received via HTTP and HTTPS protocols to the sockets specified in the settings. For this reason, the server does not have any conflicts with web servers when they operate on the same host. The secure HTTPS protocol is used for managing Dr.Web Industrial for UNIX File Servers.



It is not mandatory to install Dr.Web management web interface for the proper functioning of Dr.Web Industrial for UNIX File Servers. It can be missing. This is why the corresponding block is circled with a dashed line.

The Dr.Web HTTPD component issues commands to the Dr.Web Industrial for UNIX File Servers [Dr.Web ConfigD](#) configuration daemon, as well as to the [Dr.Web File Checker](#) component for file scanning, and to other components. These commands are based on those that were received through the provided HTTP API.



If the management web interface of Dr.Web Industrial for UNIX File Servers, which uses Dr.Web HTTPD, is included in Dr.Web Industrial for UNIX File Servers, it is described in the corresponding [section](#).

If the Dr.Web's management web interface is not included in Dr.Web Industrial for UNIX File Servers, you can connect any external management interface that uses the HTTP API by Dr.Web HTTPD for interaction (described in the section [Description of the HTTP API](#)).

## Command-Line Arguments

To run Dr.Web HTTPD, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-httpd [<options>]
```

Dr.Web HTTPD can process the following options:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-httpd --help
```

This command outputs short help information on Dr.Web HTTPD.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon when required (usually at the startup of the operating system). If the component is running and the web interface is installed, then to manage the components of Dr.Web Industrial for UNIX File Servers, you can simply use any standard web-browser to access, via HTTPS, any of the addresses at which the web-interface is served. To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To get documentation about this component of the product from the command line, use the following command: `man 1 drweb-httpd`.

## Configuration Parameters

The component uses configuration parameters which can be found in the [HTTPD] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

The section contains the following parameters:

Parameter	Description
LogLevel <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the [Root] <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
Log <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
ExePath <i>{path to file}</i>	<p>Executable path to the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-httpd</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-httpd</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-httpd</code></li></ul>
Start <i>{Boolean}</i>	<p>Launch/do not launch the component by the <a href="#">Dr.Web ConfigD</a> configuration daemon.</p> <p>When you specify the <code>Yes</code> value for this parameter, it the configuration daemon will start the component immediately; and when you specify the <code>No</code> value, the configuration daemon will terminate the component immediately.</p> <p>Default value: <i>It depends on whether product management interface is installed.</i></p>
AdminListen <i>{address, ...}</i>	<p>List of network sockets (every network socket consists of <code>&lt;IP address&gt;:&lt;port&gt;</code>) on which Dr.Web HTTPD is listening for connections (via HTTPS) from clients that have administrative privileges. These sockets are used both for connecting to the managing <a href="#">web interface</a> (if the web interface is installed) and for access to the HTTP API.</p> <p>The values in the list must be separated with commas (each value in the quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add sockets <code>192.168.0.1:1234</code> and <code>10.20.30.45:5678</code> to the list.</p>



Parameter	Description
	<p>1. Adding values to the configuration file.</p> <ul style="list-style-type: none"><li>Two values in a line:</li></ul> <pre>[HTTPD] AdminListen = "192.168.0.1:1234", "10.20.30.45:5678"</pre> <ul style="list-style-type: none"><li>Two lines (a value per line):</li></ul> <pre>[HTTPD] AdminListen = 192.168.0.1:1234 AdminListen = 10.20.30.45:5678</pre> <p>2. Adding values via the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset HTTPD.AdminListen -a 192.168.0.1:1234 # drweb-ctl cfset HTTPD.AdminListen -a 10.20.30.45:5678</pre> <p>If no value is specified, it is impossible to use the HTTP API and the web interface (if it is installed).</p> <p>Default value: <code>127.0.0.1:4443</code></p>
<code>PublicListen</code> <code>{address, ...}</code>	<p>List of network sockets (every network socket consists of <code>&lt;IP address&gt;:&lt;port&gt;</code>) on which Dr.Web HTTPD is listening for connections (via HTTP) from clients with limited privileges.</p> <p>The values in the list must be separated with commas (each value in the quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add sockets <code>192.168.0.1:1234</code> and <code>10.20.30.45:5678</code> to the list.</p> <p>1. Adding values to the configuration file.</p> <ul style="list-style-type: none"><li>Two values in a line:</li></ul> <pre>[HTTPD] PublicListen = "192.168.0.1:1234", "10.20.30.45:5678"</pre> <ul style="list-style-type: none"><li>Two lines (one value per line):</li></ul> <pre>[HTTPD] PublicListen = 192.168.0.1:1234 PublicListen = 10.20.30.45:5678</pre>



Parameter	Description
	<p>2. Adding values via the <code>drweb-ctl cfset</code> <a href="#">command</a>:</p> <pre># drweb-ctl cfset HTTPD.PublicListen -a 192.168.0.1:1234 # drweb-ctl cfset HTTPD.PublicListen -a 10.20.30.45:5678</pre> <p>At these addresses (sockets) you cannot access the full scope of the HTTP API commands or access the managing web interface.</p> <p>Default value: <i>(not set)</i></p>
<code>AdminSslCertificate</code> <i>{path to file}</i>	<p>Path to the server certificate file used by the web interface server for communication with clients that establish connections to an administrative socket via HTTPS.</p> <p>This file is generated automatically during the installation of the component.</p> <p>Please note that the certificate file and the private key file (which is specified by a parameter described below) must form a matching pair.</p> <p>Default value: <code>&lt;etc_dir&gt;/certs/serv.crt</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/etc/opt/drweb.com/certs/serv.crt</code>.</li><li>• For FreeBSD: <code>/usr/local/etc/drweb.com/certs/serv.crt</code></li></ul>
<code>AdminSslKey</code> <i>{path to file}</i>	<p>Path to private key file used by the web interface server for communication with clients that establish connections to an administrative socket via HTTPS.</p> <p>This file is generated automatically during the installation of the component.</p> <p>Please note that the certificate file (which is specified by the previous discussed parameter) and the private key file must form a matching pair.</p> <p>Default value: <code>&lt;etc_dir&gt;/certs/serv.key</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/etc/opt/drweb.com/certs/serv.key</code>.</li><li>• For FreeBSD: <code>/usr/local/etc/drweb.com/certs/serv.key</code></li></ul>
<code>AdminSslCA</code> <i>{path to file}</i>	<p>Path to a certificate file that acts as a trusted Certification Authority (CA) certificate for checking the certificates provided by the clients who are connecting to an administrative socket via HTTPS.</p> <p>If the client's certificate is signed with the certificate specified in this parameter, this client will not need to enter the login/password pair for authentication. Moreover, the login/password Authentication is prohibited for clients that use client certificates signed with the certificate set in this parameter.</p>



Parameter	Description
	<p>The client that passed this certificate-based authentication is always treated as a superuser (<i>root</i>).</p> <p>Default value: <i>(not set)</i></p>
<code>WebconsoleRoot</code> <i>{path to directory}</i>	<p>Path to the directory with the files used by the management web interface if it is installed (similar to the <code>htdocs</code> directory of an Apache HTTP Server).</p> <p>Default value: <code>&lt;opt_dir&gt;/share/drweb-httpd/webconsole</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/share/drweb-httpd/webconsole</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-httpd/webconsole</code></li></ul>
<code>AccessLogPath</code> <i>{path to file}</i>	<p>Path to the file where all HTTP/HTTPS requests from clients to the web interface server are registered.</p> <p>If not specified, HTTP/HTTPS requests are not logged to a file.</p> <p>Default value: <i>(not set)</i></p>

## Description of the HTTP API

### In this section

- [General Information](#)
- [User authentication and authorization](#)
- [Managing Dr.Web Industrial for UNIX File Servers](#)
- [Managing the list of threats](#)
- [Managing Quarantine](#)
- [Examples of using the HTTP API](#)

### 1. General Information

The HTTP API is provided as a means to control and manage Dr.Web Industrial for UNIX File Servers via the HTTP protocol (to ensure security, the HTTPS protocol is used).

Version 1.0 of the HTTP protocol is used. The API uses the standard methods of the HTTP protocol: `GET` and `POST`. All data is transferred in the form of JSON objects, except as otherwise specified. If you are sending a JSON object in the body of your HTTP `POST` request, use the `Content-Type: application/json` header with `application/json` as its value.



### The format of an HTTP response to an HTTP request

- In responses to all requests, except as otherwise specified, JSON objects are returned. If an error occurs while processing a request, an [Error](#) JSON will be returned.
- If a JSON object sent as a response has a field of an Array type, but this array does not contain any elements, this field will be omitted in the response from the server.
- In all responses, except as otherwise specified, the `Content-Type:` header field has the `application/json` value.
- If the client requests an endpoint that does not exist, an [Error](#) JSON object with `EC_UNEXPECTED_MESSAGE` in the `code` field will be returned.
- If SCS (*Secure Cookie Sessions for HTTP*) is used (see [below](#)), the responses contain the SCS cookie.

### Encoding of strings in JSON objects

- The strings are transmitted in UTF-8 encoding (without BOM). Symbols that are not part of the ASCII table are not escaped with sequences like `\uXXXX` in the outgoing JSON strings, but are transmitted in UTF-8 encoding.
- Strings in the incoming JSON objects may contain both UTF-8 encoded symbols and escaped sequences like `\uXXXX`.

### General restrictions of data transmission

- In POST-requests with JSON objects in the body any symbols complying with [RFC 7159](#) are allowed.
- In GET-requests any symbols complying with [RFC 1945](#) are allowed in the URI.
- Symbols complying with [RFC 1945](#) can be used in any other part of the request (either in the headers or in the body).

## 2. User authentication and authorization

To start using the API you should be authenticated by the server. Two means of authorization are provided.

1. [Using SCS](#), according to [RFC 6896](#).
2. [Using clients' SSL certificates](#) that are signed with a special certificate which Dr.Web HTTPD regards as a trusted CA's certificate. In this case the client is treated as if the client had successfully input root credentials to get authorization (X.509 client certificates are used).

If a SCS is used, the cookies confirming the authentication are transferred in the headers:

`Cookie:` in the request and `Set-Cookie:` in the response.

When authorizing with an SSL certificate, no cookies are used.





When authorizing with SCS, using the API starts with sending the `login` command. If this command is executed successfully, an SCS cookie is sent to the client in the response. When authorizing with a client certificate, you do not need to run the `login` command. If you try to execute it, an [Error](#) JSON object will be returned in the response.

## 2.1. Via specifying login and password (SCS)

User authentication and authorization commands:

API command	Description
<code>login</code>	<p><b>Action:</b> Authenticate the client based on the specified user name and password and authorize the client to use the HTTP API commands. If the authentication is successful, an SCS cookie will be returned.</p> <p>URI: <code>/api/10.2/login</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> <a href="#">AuthOptions</a> object</p> <p><b>Result of successful execution:</b> an empty object, SCS cookie</p>
<code>logout</code>	<p><b>Action:</b> Revoke the provided SCS cookie. After that, in response to any HTTP API call that contains the revoked SCS cookie an <a href="#">Error</a> object will be returned that will contain the <code>EC_NOT_AUTHORIZED</code> error code.</p> <p>URI: <code>/api/10.2/logout</code></p> <p><b>HTTP method:</b> GET</p> <p><b>Input parameters:</b> SCS cookie</p> <p><b>Result of successful execution:</b> an empty object</p>
<code>whoami</code>	<p><b>Action:</b> Display the name of the authenticated user.</p> <p>URI: <code>/api/10.2/whoami</code></p> <p><b>HTTP method:</b> GET</p> <p><b>Input parameters:</b> (SCS cookie)*</p> <p><b>Result of successful execution:</b> <a href="#">whoami</a> object, (SCS cookie)</p>

\*) Here and below the SCS cookie is given in parentheses, because sending/receiving it is required only if authorization via SCS is used.



The `login` и `logout` commands are used only when authenticating with SCS.



## Description of used objects

1) `AuthOptions`—an object that contains the login data of a user that needs to be authenticated and authorized to use the full HTTP API:

```
{
  "user": string, //User name
  "password": string //User's password
}
```



You can specify a user who is a member of the admin group (`sudoers` in Debian and Ubuntu, `wheel` in CentOS and Fedora, `astra-admin` in Astra Linux, etc). If the user is not a member of the admin group, the `EC_NOT_AUTHORIZED` error will be returned in the response.

2) `whoami`—an object that contains the name of the user that was authorized to use the HTTP API:

```
{
  "whoami" :
  {
    "user": string //User name
  }
}
```

3) `Error`—an object that contains Information about an error that has occurred:

```
{
  "error" :
  {
    "code" : string, //A string specifying an error code that looks like
    EC_XXX
    *"what": string //Description of the error
  }
}
```

Asterisk-marked parameter is optional.



The [Error](#) JSON object that is returned in response to a HTTP API command if an error occurs while processing the request, has a `code` field that contains not a numeric error code, but an internal string-type code that is used by the components of Dr.Web Industrial for UNIX File Servers. This code is a string that looks like `EC_XXX`. To find out the corresponding numeric code and to get detailed information about the error please refer to the [Known Errors](#) section (in the Appendix F to the Administrator Manual).



## 2.2. Authentication using a personal certificate

Authentication with an SSL certificate supposes using the personal certificate is signed by a certificate authority certificate specified in the Dr.Web HTTPD settings as trusted. If you are authenticated with a certificate, all your requests are considered a made on behalf of the *root* user.

### To authorize with a personal user certificate

1. Create a personal certificate signed by a certificate authority certificate.
2. In the Dr.Web HTTPD [settings](#) (parameter `AdminSSLCA`), specify a path to the authority certificate by which your personal certificate is signed.
3. Each time you connect to Dr.Web HTTPD, use a signed certificate.

If necessary, refer to the [Appendix E. Generating SSL certificates](#) section.

## 3. Managing Dr.Web Industrial for UNIX File Servers

API commands for viewing and modifying the current values of configuration parameters:

API command	Description
<i>Configuration management commands</i>	
<code>get_lexmap</code>	<p><b>Action:</b> Get the parameter values of the current configuration (called a "lexical map" of parameters here).</p> <p>URI: <code>/api/10.2/get_lexmap</code></p> <p><b>HTTP method:</b> GET</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> <a href="#">LexMaps</a> object, (SCS cookie)</p>
<code>set_lexmap</code>	<p><b>Action:</b> Set or reset (to defaults) the specified parameters of the current configuration (sent as a "lexical map" of parameters).</p> <p>URI: <code>/api/10.2/set_lexmap</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie), <a href="#">LexMap</a> object</p> <p><b>Result of successful execution:</b> <a href="#">SetOptionResult</a> object, (SCS cookie)</p>
<i>Updating commands</i>	
<code>start_update</code>	<p><b>Action:</b> Launch update.</p>



API command	Description
	<p>URI: <code>/api/10.2/start_update</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> the <a href="#">StartUpdate</a> object, (SCS cookie)</p>
<code>stop_update</code>	<p><b>Action:</b> Stop active updating process.</p> <p>URI: <code>/api/10.2/stop_update</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> an empty object, (SCS cookie)</p>
<code>baseinfo</code>	<p><b>Action:</b> View the information on the downloaded viral bases.</p> <p>URI: <code>/api/10.2/baseinfo</code></p> <p><b>HTTP method:</b> GET</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> the <a href="#">BaseInfoResult</a> object including the <a href="#">VirusBaseInfo</a> object (SCS cookie)</p>
<i>Licence management commands</i>	
<code>install_license</code>	<p><b>Action:</b> Install the specified key file.</p> <p>URI: <code>/api/10.2/install_license</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie), key file body (or an archive with the key file)</p> <p><b>Result of successful execution:</b> an empty object, (SCS cookie)</p>
<i>Commands for connection to the centralized protection server</i>	
<code>esconnect</code>	<p><b>Action:</b> Enable the centralized protection mode.</p> <p>URI: <code>/api/10.2/esconnect</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie), the <a href="#">ESConnection</a> object</p>



API command	Description
	<b>Result of successful execution:</b> an empty object, (SCS cookie)
esdisconnect	<b>Action:</b> Disable the centralized protection mode.  URI: /api/10.2/esdisconnect  <b>HTTP method:</b> POST  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> an empty object, (SCS cookie)

Configuration of the product components is returned and set as a so called *lexical map*, i.e. as a sequence of parameter-value pairs. A [LexMaps](#) object always contains three enclosed [LexMap](#) objects):

- *active*—the current values of the parameters;
- *hardcoded*—default values automatically assigned to the parameters whose values are missing or invalid;
- *master*—the values of configuration parameters set by the client.



The `get_lexmap` command always returns all three sets of configuration parameter values for all the components that can be included in Dr.Web Industrial for UNIX File Servers, not only for those that are actually installed and running.

## Description of JSON objects

1) [LexMaps](#)—an object that contains the active, the default and the user-set lexical maps of parameter values:

```
{
  "active": LexMap, //Active (current) values of configuration parameters
  "hardcoded": LexMap, //Default values of configuration parameters
  "master": LexMap //Configuration parameter values set
  //by the user
}
```

Each of these fields is a [LexMap](#) object, which in turn contains an array of [LexOption](#) objects.

2) [LexMap](#)—an object that contains a lexical map of parameters:

```
{
  "option": LexOption[] //Array of configuration options
}
```

3) [LexOption](#)—an object that contains a single parameter or a section of the configuration (a section is a group of parameters):



```
{
  "key": string, //Name of the option (configuration parameter/section)
  * "value": LexValue, //If this option is a single parameter
  * "map": LexMap //If this option is a section
}
```

Asterisk-marked parameters are optional.

The [LexOption](#) object represents a section or a single parameter of the Dr.Web Industrial for UNIX File Servers configuration. It always has a `key` field that corresponds to the name of the section or to the name of the single parameter. Besides this, depending on what this object describes—a single parameter or a section—the object also contains either a `value` field (in case it describes a single parameter), or a `map` field (in case it describes a section). Any section is also an object of the [LexMap](#) type; whereas the value of a single parameter is an object of the [LexValue](#) type that contains an `item` field specifying the parameter value in the string format.

- 4) [LexValue](#)—an object that contains the array of values assigned to a parameter:

```
{
  "item": string[] //Array of parameter values
}
```

As its input, the `set_lexmap` command accepts a [LexMap](#) object, which must contain all the parameters whose values you want to change to new ones or want to reset to their defaults. Those parameters that you want to reset to their default values must not contain the `value` field. Parameters that are not mentioned in the lexical map given by you in the `set_lexmap` command will not be changed. As a result of its execution, the `set_lexmap` command returns a [SetOptionResult](#) object that will contain the results of changing every parameter that was specified in your command.

- 5) [SetOptionResult](#)—an object with an `item` field that contains an array of results of parameter changes:

```
{
  "item": SetOptionResultItem[] //Array of results
}
```

The object contains an array of [SetOptionResultItem](#) objects that describe the results of making changes to every parameter specified in your command.

- 6) [SetOptionResultItem](#)—an object that contains information about a making a change to a value of some parameter:

```
{
  "option": string, //Name of the parameter
  "result": string, //Result of changing the value (error code)
  * "lower_limit": string, //The lowest permitted value
  * "upper_limit": string //The highest permitted value
}
```

Asterisk-marked parameters are optional.



The `option` field contains the name of the parameter to which your action was applied, and the `result` field contains the result of an attempt to change the value of this parameter. If the new value was assigned successfully to a parameter, then this field will contain `EC_OK`. In case of an error (if this field is not equal to `EC_OK`), this object may optionally contain an `lower_limit` field and an `upper_limit` field that hold the maximum and the minimum permitted value for this parameter.

7) The `StartUpdate` object contains data on the started update process:

```
{
  "start_update":
  {
    "attempt_id" : number //Identifier of a launched updating process
  }
}
```

8) The `ESConnection` object contains data on the started update process:

```
{
  *"server": string,      //<Host address>:<port> (without the http/https
  prefix)
  "certificate": string, //Base64 server key
  *"newbie": boolean,    //False by default
  *"login": string,      //User name
  *"password": string    //Password
}
```

Asterisk-marked parameters are optional.

The parameters `login` and `password` are only specified if `newbie = true`.

Before connecting, download the certificate file from the centralized protection server and execute the command:

```
$ cat certificate.pem |base64
```

The string obtained from executing this command is used as the parameter value for `certificate`.

9) The `BaseInfoResult` object contains data on the downloaded viral bases:

```
{
  "vdb_base_stamp" : number //Timestamp of the base
  "vdb_bases" : VirusBaseInfo[] //Detailed information upon the base
}
```

10) The `VirusBaseInfo` object contains the information on each virus base:

```
{
  "path" : string //Path to the base file
  "virus_records" : number //The number of records in the base
  "version" : number //Base version
  "timestamp" : number //Base timestamp
  "md5" : string //base MD5-hash
  "load_result" : string //The result of downloading the base (EC_OK if
  the base has been downloaded successfully)
```



```
*"sha1" : string - base SHA1-hash  
}
```

Asterisk-marked parameter is optional.

## 4. Object Scanning

API commands for scanning objects:

API command	Description
<i>Data scanning (using the Dr.Web Network Checker component call)</i>	
scan_request	<b>Action:</b> Order of connection ( <i>endpoint</i> ) to scan data with the necessary parameters.  URI: /api/10.2/scan_request  <b>HTTP method:</b> POST  <b>Input parameters:</b> (SCS cookie), the <a href="#">ScanOptions</a> object  <b>Result of successful execution:</b> the <a href="#">ScanEndpoint</a> object, (SCS cookie)
scan_endpoint	<b>Action:</b> Launch of data scanning (for instance, file body) at the created <i>endpoint</i> connection.  URI: /api/10.2/scan_endpoint/<endpoint>  <b>HTTP method:</b> POST  <b>Input parameters:</b> (SCS cookie), verifiable data  <b>Result of successful execution:</b> the <a href="#">ScanResult</a> object, (SCS cookie)
scan_path	<b>Action:</b> Scanning a file or a directory located on the path specified.  URI: /api/10.2/scan_path  <b>HTTP method:</b> POST  <b>Input parameters:</b> (SCS cookie), <a href="#">ScanPathOptions</a> object  <b>Result of successful execution:</b> the <a href="#">ScanPathResult</a> object, (SCS cookie)
scan_stat	<b>Action:</b> Viewing scan statistics.  URI: /api/10.2/scan_stat  <b>HTTP method:</b> GET  <b>Input parameters:</b> (SCS cookie), statistics format (JSON or CSV)





API command	Description
	<p><b>Result of successful execution:</b> the <a href="#">ScanStat</a> object (if JSON format is selected), (SCS cookie)</p> <p>If CSV format is selected, a table whose columns correspond to the fields the <a href="#">ScanStat</a> is returned.</p>

## Description of JSON objects

1) ScanOptions is the object that contains parameters used for creating *endpoint* for file scanning:

```
{
  "scan_timeout_ms": number, //A time-out to scan one file, in ms
  "cure": boolean, //Apply cure to infected file
  "heuristic_analysis": boolean, //Use heuristic analysis
  "packer_max_level": number, //Maximum nesting level for packed objects
  "archive_max_level": number, //Maximum nesting level for archives
  "mail_max_level": number, //Maximum nesting level for email messaged
  "container_max_level": number, //Maximum nesting level for other compound
objects (containers)
  "max_compression_ratio": number, //Maximum a compression value
  "min_size_to_scan" : number, //Minimal size of an object to be scanned
  "max_size_to_scan" : number, //Maximum size of an object to be scanned
  "threat_hash" : boolean //Return SHA1 and SHA256 of all threats
}
```

2) ScanPathOptions is the object that contains parameters used for scanning a file or a directory located on the path specified:

```
{
  "path" : string //Absolute path to the file or the directory to be
scanned
  *"exclude_path" : string[] //List of the paths excluded from scanning
(it is allowed to use masks)
  *"scan_timeout_ms" : number //Scan timeout for an object
  *"archive_max_level" : number//Maximum nesting level for archived
objects
  *"packer_max_level" : number //Maximum nesting level for packed
objects
  *"mail_max_level" : number //Maximum nesting level for email messages
  *"container_max_level" : number//Maximum nesting level for other
compound objects (containters)
  *"max_compression_ratio" : number//Maximum compression value
  *"heuristic_analysis" : bool //Use heuristic analysis (true by
default)
  *"follow_symlinks" : bool //Follow symbolic links
  *"min_size_to_scan" : number //Minimal size of an object to be scanned
  *"max_size_to_scan" : number //Maximal size of an object to be scanned
  *"timeout_ms" : number - //Scan timeout for all objects
  *"threat_hash" : bool - //Return SHA1 and SHA256 of all threats
}
```



Asterisk-marked parameters are optional.

3) ScanPathResult is an object that contains results of the scanning of the object located on the path specified:

```
{
  ScanPathResult:
    "results": ScanResult[] //Scan results
    *"error": string //Error if the scanning process terminated (the
    scanning timeout is expired, for instance)
}
```

Asterisk-marked parameter is optional.

If the scanning is successful, the error string is not included in the response.

4) ScanResult is an object that contains the results of scanning:

```
{
  ScanResult:
    "scan_report" : ScanReport //The information upon the threat found
    *"sha1" : string //The SHA1 hash of the threat
    *"sha256" : string //The SHA256 hash of the threat
}
```

Asterisk-marked parameters are optional.

5) ScanReport is an object that contains information about the file in which the threat was found:

```
{
  ScanReport:
  "object" : string //Name of the object scanned
    For a file //The absolute path, for a nested object - the name of the
    file
    Always points to temporary file when calling scan_endpoint
  *"size" : number //Object size
  *"compressed_size" : number //Object size before extraction
  *"core_fingerprint" : string //Scan engine fingerprint
  *"packer" : string[] //The list of packers used to pack the object
  *"compression_ratio" : number //Archive compression ratio
  *"archive" : Archive //Information on the archive or container type, if
  the object scanned was identified as an archive or a container
  *"virus" : Virus[] //Viruses detected in the objects (if found)
  *"item" : ScanReport[] //Reports on scanning of the nested objects (if
  there were some)
  *"error" : string //Scanning error (if occurred)
  *"heuristic_analysis" : bool //Indicates if heuristic analysis was used
  *"cured" : bool //The object was cured
  *"cured_by_deletion" : bool //The object was deleted.
  *"new_path" : string //The new path to the object renamed when being cured
  *"user_time" : number //Type spent for syscalls when scanning
  *"system_time" : number //Time spent in the userspace
}
```

Asterisk-marked parameters are optional.



The fields `virus` and `error` may be absent if no threats are detected and no errors occur during the scan. To call `scan_endpoint`, the `scan_endpoint` field always specifies a temporary file, created by the Dr.Web Network Checker component in the local server file system and containing the data for scanning, sent in the body of the `scan_endpoint` request.

6) `ScanEndpoint` is an object that contains data on the *endpoint*, created for file scanning:

```
{
  "endpoint": string //Unique identifier of the created endpoint
}
```

The `endpoint` string, returned in the object body, is used to launch file scanning with the `scan_endpoint` command (part of URI).

7) `VirusInfo` is an object that contains information on the detected threat:

```
{
  "type": string, //Type of the detected threat
  "name": string //Name of the threat
}
```

The `type` field (threat type) is the string `SE_XXX`:

- `SE_KNOWN_VIRUS` is a known virus;
- `SE_VIRUS_MODIFICATION` is a modification of known malware;
- `SE_UNKNOWN_VIRUS` is an unknown virus (suspicious object);
- `SE_ADWARE` is adware;
- `SE_DIALER` is a dialer program;
- `SE_JOKE` is a joke program;
- `SE_RISKWARE` is a potentially dangerous program;
- `SE_HACKTOOL` is a hacktool.

8) `Archive` is an object that contains information on archives, packed objects, e-mail messaged and other containers:

```
{
  "type" : string - the type of the archive:
    "SE_ARCHIVE" - archive
    "SE_MAIL" - e-mail message
    "SE_CONTAINER" - other container
  "name" : string - archive format
}
```

9) `ScanStat` is an object that contains the scanning statistics:

```
{
  "origin": string //The application by the request of which the scanning
was initialized
  #Counters for infected objects:
  "known_virus": number //Number of objects infected by known viruses
}
```



```
"virus_modification": number //Number of objects infected by
modifications of known viruses
"unknown_virus": number //Number of objects infected by unknown
viruses
"adware": number //Number of objects with SE_ADWARE
"dialer": number //Number of objects with SE_DIALER
"joke": number //Number of objects with SE_JOKE
"riskware": number //Number of objects with SE_RISKWARE
"hacktool" : number //Number of objects with SE_HACKTOOL
"cured": number //Number of cured threats
"quarantined": number //Number of quarantined threats
"deleted": number //Number of deleted threats
}
```

## 5. Managing the list of threats

To manage the list of threats that have been detected during a scanning or by the file system monitor—SpIDer Guard—the following commands are available in the HTTP API:

API command	Description
threats	<b>Action:</b> List identifiers of all detected threats.  URI: /api/10.2/threats/  <b>HTTP method:</b> GET  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> Array of threat identifiers
threat_info	<b>Action:</b> Get information about a threat by its identifier—<threat ID>.  URI: /api/10.2/threat_info/<threat ID>  <b>HTTP method:</b> GET  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> (SCS cookie), <a href="#">FileThreat</a> object
cure_threat	<b>Action:</b> Try to cure a threat specified by its identifier—<threat ID>.  URI: /api/10.2/cure_threat/<threat ID>  <b>HTTP method:</b> POST  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> (SCS cookie), an empty object



API command	Description
<code>delete_threat</code>	<p><b>Action:</b> Delete the file that contains the threat specified by the threat identifier—<i>&lt;threat ID&gt;</i>.</p> <p>URI: <code>/api/10.2/delete_threat/&lt;threat ID&gt;</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> (SCS cookie), an empty object</p>
<code>ignore_threat</code>	<p><b>Action:</b> Ignore a threat specified by its identifier—<i>&lt;threat ID&gt;</i>.</p> <p>URI: <code>/api/10.2/ignore_threat/&lt;threat ID&gt;</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> (SCS cookie), an empty object</p>
<code>quarantine_threat</code>	<p><b>Action:</b> Quarantine a threat specified by its identifier—<i>&lt;threat ID&gt;</i>.</p> <p>URI: <code>/api/10.2/quarantine_threat/&lt;threat ID&gt;</code></p> <p><b>HTTP method:</b> POST</p> <p><b>Input parameters:</b> (SCS cookie)</p> <p><b>Result of successful execution:</b> (SCS cookie), an empty object</p>

Each threat found in the specified application has a unique numeric integer identifier *<threat ID>*. The list of all identifiers is returned by the `threats` command. In the `threat_info`, `cure_threat`, `delete_threat`, `ignore_threat`, and `quarantine_threat` commands only the identifiers returned by the `threats` command are allowed.

All information on the specified threat, including actions history, can be obtained using the `threat_info` request. The information is returned as the [FileThreat](#) object.

## Description of JSON objects

1) `FileThreat` is an object that contains the following data:

```
{
  "threat_id": number, //Threat identifier
  "detection_time": UNIXTime, //Time when the threat was detected
  "report": ScanReport, //Report about scanning the file
  "stat": FileStat, //Information about the file
  "origin": string, //Name of the component that detected the threat
}
```



```
"origin_pid": number, //PID of the component that detected the threat
"task_id": number, //Identifier of the scanning task
//in the scan engine
"history": ActionResult[] //History of actions applied to the threat (an
array)
}
```

The `report` field contains the [ScanReport](#) object; the `stat` field contains a [FileStat](#) object, and the `history` field contains an array of [ActionResult](#) objects (the history of actions applied to the file).

2) `ScanReport` is an object that contains information about the file in which the threat was found:

```
{
  "object": string, //File system object that contains the threat
  "size": number, //Size (in bytes) of the file that contains the threat
  "virus": VirusInfo[], //List of details about the found
  //threats
  *"error": string, //An error message
  "heuristic_analysis": bool //Flag that shows whether heuristic
  //analysis was used
}
```

Asterisk-marked parameter is optional.

The `virus` field is an array of [VirusInfo](#) objects containing information about all detected threats. The `error` field is only present if an error has occurred.

3) `FileStat` is an object that contains file statistics:

```
{
  "dev": number, //Device containing the file
  "ino": number, //The file inode number
  *"size": number, //Size of the file
  *"uid": User, //User ID of the file's owner
  *"gid": Group, //Group ID of the owning group
  *"mode": number, //The mode of access to the file
  *"mtime": UNIXTime, //Date/time when the file was last modified
  *"ctime": UNIXTime //Date/time when the file was created
  *"rsrc_size": number, //
  *"finder_info": string, //
  *"ext_finder_info": string, //
  *"uchg": string, //
  *"volume_name": string, //Volume name
  *"volume_root": string, //Root (mount point) of the volume
  *"xattr": XAttr[] //Extended information about the file
}
```

Asterisk-marked parameters are optional.

The `xattr` field contains an array of `XAttr` objects. This object contains two *string*-type fields: `name` and `value`. The `uid` and `gid` fields contain a `User` and a `Group` object respectively, that have information about the file owner and the group owning the file respectively. These objects contain two fields each:



- uid (gid)—the numeric ID of the user (group);
- username (groupname)—name of the user (group) as a string.

4) `ActionResult` is an object that contains information on the action applied to the file and the result:

```
{
  "action": string, //The action applied
  "action_time": UNIXTime, //Date/time when the action was applied
  "result": string, //Result of applying the action
  "cure_report": ScanReport //Report about applying the action
}
```

The `cure_threat`, `delete_threat`, `ignore_threat` and `quarantine_threat` commands return an empty object when executed successfully. If the requested action fails, [Error](#) object is returned.

## 6. Managing Quarantine

To manage quarantined objects the following commands are available in the HTTP API:

API command	Description
<code>quarantine</code>	<b>Action:</b> List identifiers of quarantined objects.  URI: <code>/api/10.2/quarantine/</code>  <b>HTTP method:</b> GET  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> (SCS cookie), array of <a href="#">QuarantineId</a> objects (objects in quarantine)
<code>qentry_info</code>	<b>Action:</b> Get information about a quarantined object specified by its identifier— <code>&lt;entry ID&gt;</code> .  URI: <code>/api/10.2/qentry_info/&lt;entry ID&gt;</code>  <b>HTTP method:</b> GET  <b>Input parameters:</b> (SCS cookie)  <b>Result of successful execution:</b> (SCS cookie), <a href="#">QEntry</a> object
<code>cure_qentry</code>	<b>Action:</b> Try to cure a quarantined object specified by its identifier— <code>&lt;entry ID&gt;</code> .  URI: <code>/api/10.2/cure_qentry/&lt;entry ID&gt;</code>  <b>HTTP method:</b> POST



API command	Description
	<b>Input parameters:</b> (SCS cookie) <b>Result of successful execution:</b> (SCS cookie), an empty object
delete_qentry	<b>Action:</b> Delete a quarantined object specified by its identifier— <i>&lt;entry ID&gt;</i> . URI: /api/10.2/delete_qentry/ <i>&lt;entry ID&gt;</i> <b>HTTP method:</b> POST <b>Input parameters:</b> (SCS cookie) <b>Result of successful execution:</b> (SCS cookie), an empty object
restore_qentry	<b>Action:</b> Restore a quarantined object specified by its identifier— <i>&lt;entry ID&gt;</i> —to its original location. URI: /api/10.2/restore_qentry/ <i>&lt;entry ID&gt;</i> <b>HTTP method:</b> POST <b>Input parameters:</b> (SCS cookie) <b>Result of successful execution:</b> (SCS cookie), an empty object

Each quarantined object has a unique identifier. The list of identifiers represented as of [QuarantineId](#) is returned by the `quarantine` command. The identifier consists of two parts: `chunk_id` and `entry_id`.

### Description of JSON objects

1) `QuarantineId` is an object that contains both parts of the two-part identifier of a quarantined object:

```
{
  "chunk_id": string,
  "entry_id": string
}
```

These two fields together make up the identifier of a quarantined object. To apply any action to a quarantined object with the help of the `qentry_info`, `cure_qentry`, `delete_qentry` or `restore_qentry` commands, you should specify the quarantined object general identifier—*<entry ID>*—written in the form of *<entry\_id>@<chunk\_id>*. The `qentry_info` command allows to get the detailed information about a quarantined object with a specified identifier. This command returns a [QEntry](#) object.

2) `QEntry` is an object that contains information about a quarantined object:





```
{
  "entry_id": string, //Parts of the identifier of
  *"chunk_id": string, //this quarantined object
  *"quarantine_dir": string, //Quarantine directory
  "restore_path": string, //path where the quarantined
  //object will be restored
  "creation_time": number, //Date/time of moving to quarantine
  //(in UNIX time)
  "report": ScanReport, //Report about scanning the object
  //(see ScanReport described above)
  "stat": FileStat, //Statistical information about the file
  //(see FileStat described above)
  *"history": QEntryOperation[], //History of operations performed on the
  object
  *"who": RemoteUser, //The remote owner of the file (if
  //the file was quarantined from a file server
  //storage)
  *"detection_time": number, //Date/time of detecting the threat
  *"origin": string, //Component that detected the threat
}
```

Asterisk-marked parameters are optional.

The `report` field contains a [ScanReport](#) object; the `stat` field contains a [FileStat](#) object, and the `history` field contains the history of actions applied to the isolated object. Each action entry is described by a [QEntryOperation](#) object. The optional `who` field contains information about the deleted user in the form of a [RemoteUser](#) object.

3) `QEntryOperation` is an object that contains data on operations applied to the quarantined object:

```
{
  "action": string, //Operation performed on the object
  //(see the possible values below)
  "action_time": number, //Date/time when the operation was performed (UNIX
  Time)
  "result": string, //Error when trying to perform the operation (a code
  //EC_XXX)
  *"restore_path": string, //path for restoring the quarantined object
  //(if action = "QENTRY_ACTION_RESTORE")
  *"rescan_report": ScanReport //Report about rescanning (if
  //action = "QENTRY_ACTION_RESCAN")
}
```

Asterisk-marked parameters are optional.

The `action` field can have the following values:

- `QENTRY_ACTION_DELETE` is an attempt to remove the quarantined object;
- `QENTRY_ACTION_RESTORE` is an attempt to restore the quarantined object;
- `QENTRY_ACTION_RESCAN` is an attempt to rescan the quarantined object;
- `QENTRY_ACTION_CURE` is an attempt to cure the quarantined object.

4) `RemoteUser` is an object that contains information about the remote user that owns the file (if the file was relocated to quarantine from the file server storage):



```
{
  *"ip": string, //IP-address of the user
  *"user": string, //User name
  *"domain": string //Domain of the user
}
```

Asterisk-marked parameters are optional.

The `cure_gentry`, `delete_gentry` and `restore_gentry` commands return an empty object if the command execution was successful. In case the requested operation on a quarantined object finished with an error (for instance, the file could not be restored), then, instead of an empty object, an [Error](#) object will be returned.

## 7. Examples of using the HTTP API

To test the work of the HTTP API, you can use the `curl` utility. The general format of an API call is given below.

```
$ curl https://<HTTPD.AdminListen>/<HTTP API URI> -k -X <HTTP method name>
[-H 'Content-Type: application/json' --data-binary '@<file of the JSON object>']
[-c <cookie file> [-b <cookie file>]] [> <file of the result>]
```

- the `-k` option specifies `curl` not to verify the SSL certificate;
- the `-X` options specifies the HTTP method used (GET or POST);
- the `-H` option is used to add the `Content-Type: application/json` header;
- the `--data-binary` (or `-d`) option is used to add a JSON object saved in a text file to the request;
- if an SCS is used to get authorization, the files that contain the sent and received SCS cookies need to be specified with the `-b` and `-c` parameters respectively.

For the detailed description of the `curl` options refer to the man page (perform `curl --help` or `man curl` command).

1. **Authenticate and authorize a client** by specifying a user name and a password (for an SCS).

An [AuthOptions](#) object in the JSON format must be written in advance to a file named `user.json`. For example:

```
{"user": "<username>", "password": "<passphrase>"}
```

Request:

```
$ curl https://127.0.0.1:4443/api/10.2/login -k -X POST -H 'Content-Type:
application/json' --data-binary '@user.json' -c cookie.file
```

Response:

```
HTTP/1.0 200 OK
Content-Type: application/json
```



```
Content-Length: 2
Set-Cookie:
DWTOKEN=6QXy4wn_JGov9A1GohWP_kvMK3dN6ccKegjNgKcmHpb_AqSrHg9cNX_yFJhxDgr|
MTQ2Mjg3Mzg4NQ==|cWd4Ow==|GywBUVOhU4w2LF_BKT5frg==|
kR_rip5nrpxWjJ2dfZ7Xfmvi3rE=; Secure; HttpOnly; Max-Age: 900; Path=/
Pragma: no-cache

{}
```

The Set-Cookie header field contains an SCS cookie that should be used in all further requests to the HTTP API. The body of the response contains an empty object, if the authentication and authorization were successful. If the user has not been authorized, an **Error** object is returned:

```
HTTP/1.0 403 Forbidden
Content-Type: application/json
Content-Length: 35
Pragma: no-cache

{"error":{"code":"EC_AUTH_FAILED"}}
```

## 2. Get the information about the threat with *ID* = 1:

Request:

```
$ curl https://127.0.0.1:4443/api/10.2/threat_info/1 -k -X GET -c
cookie.file -b cookie.file
```

Response:

```
HTTP/1.0 200 OK
Content-Type: application/json
Content-Length: 574
Set-Cookie: DWTOKEN=<...>;
Secure; HttpOnly; Max-Age: 900; Path=/
Pragma: no-cache

{"threat_id":1,"detection_time":1462881660,
"report":{"object":"/sites/sitel/eicar.com.txt","size":68,"packer":[],
"virus":[{"type":"SE_KNOWN_VIRUS","name":"EICAR Test File (NOT a
Virus!)"}]},
"heuristic_analysis":true,"core_fingerprint":"0D2DD5A869DAB7AE354153A4D5F7
0F45",
"item":[],"log":[],"user_time":0,"system_time":0,"stat":
{"dev":2049,"ino":898,
"size":68,"uid":{"uid":1000,"username":"user"},"gid":
{"gid":1000,"groupname":"user"},
"mode":33204,"mtime":1441028214,"ctime":1460738554,"xattr":[]},
"origin":"APP_COMMAND_LINE_TOOL","origin_pid":2726,"task_id":1,"history":
[]}
```

## 3. Move to quarantine the threat with *ID* = 1:

Request:



```
$ curl -v -c cookie.jar -b cookie.jar -k -X POST -H 'Content-Type:application/json' https://127.0.0.1:4443/api/10.2/quarantine_threat/1
```

Response:

```
HTTP/1.0 200 OK
Content-Type: application/json
Content-Length: 2
Set-Cookie: DWToken=<...>; Secure; HttpOnly; Max-Age: 900; Path=/
Pragma: no-cache

{}
```

#### 4. View the information on the quarantined (isolated) object with the specified ID:

Request:

```
$ curl -v -k -X GET -c cookie.jar -b cookie.jar
https://127.0.0.1:4443/api/10.2/qentry_info/3070d3ce-7b6e-4143-9d9f-89ba3473a781@801:2108d
```

Response:

```
HTTP/1.0 200 OK
Content-Type: application/json
Content-Length: 781
Set-Cookie: DWToken=<...>; Secure; HttpOnly; Max-Age: 900; Path=/
Pragma: no-cache

{"entry_id":"3070d3ce-7b6e-4143-9d9f-89ba3473a781","chunk_id":"3830313A3231303864",
"quarantine_dir":"2F686F6D652F757365722F2E636F6D2E64727765622E71756172616E74696E65",
"restore_path":"2E2E2F7473742F65696361722E636F6D2E747874","creation_time":1462888884,
"report":{"object":"/home/user/tst/eicar.com.txt","size":68,"packer":[],
"virus":[{"type":"SE_KNOWN_VIRUS","name":"EICAR Test File (NOT a Virus!)"}]},
"heuristic_analysis":true,"core_fingerprint":"467CD4C6D423C55448B71CD5B8152776",
"item":[],"log":[],"user_time":0,"system_time":0,"stat":
{"dev":2049,"ino":898,
"size":68,"uid":{"uid":1000,"username":"user"},"gid":
{"gid":1000,"groupname":"user"},
"mode":33204,"mtime":1441028214,"ctime":1462888421,"xattr":[],"history":
[],
"detection_time":1462888667,"origin":"APP_COMMAND_LINE_TOOL"}
```



## Dr.Web SNMPD

Dr.Web SNMPD is an SNMP agent designed to integrate Dr.Web Industrial for UNIX File Servers with monitoring systems running the SNMP protocol. This integration allows you to track the status of the Dr.Web Industrial for UNIX File Servers components, as well as collect statistics on the detection and neutralization of threats. The agent supports providing monitoring systems or any SNMP managers with the following information:

- Status of any Dr.Web Industrial for UNIX File Servers component.
- Number of detected threats of various types (according to the Dr.Web classification).

Moreover, the agent sends SNMP trap notifications upon detection of a threat and upon failures in neutralization of detected threats. The agent supports SNMP protocol of version 2c and 3.

Description of the information which can be sent by the agent is stored in a special section of MIB (*Management Information Base*) created by Doctor Web. In the MIB section, defined by Dr.Web for UNIX-like operating systems, the following information is specified:

1. Formats of SNMP trap notifications about detection and neutralizing of threats and about errors related to the Dr.Web Industrial for UNIX File Servers components.
2. Dr.Web Industrial for UNIX File Servers operation statistics.
3. Dr.Web Industrial for UNIX File Servers component status.

For more details about information that can be obtained over the SNMP protocol, refer to the corresponding [section](#).

## Operating Principles

### In this section

- [General Information](#)
- [Integration with the System SNMP Agent](#)

### General Information

By default, the component is run automatically upon Dr.Web Industrial for UNIX File Servers startup. When run, the component structures data according to the structure described in MIB Dr.Web and waits for requests to receive data from external SNMP managers. The component receives information on the status of the Dr.Web Industrial for UNIX File Servers components and notifications on detected threats directly from the [Dr.Web ConfigD](#) configuration daemon.

Threats can be detected by the scan engine during scanning initiated by Dr.Web Industrial for UNIX File Servers components. Once any of threats is detected, the appropriate count (of this threat type) is incremented by one and all SNMP managers that can receive notifications get an SNMP trap notifying on the detected threat.



Collected values of counters (for example, counters of detected threats) are not saved between launches of Dr.Web SNMPD. Thus, once Dr.Web SNMPD is relaunched for any reason (including general restart of Dr.Web Industrial for UNIX File Servers), the collected values of counters are reset to zero.

## Integration with the System SNMP Agent

To enable correct operation of Dr.Web SNMP agent if the main system SNMP agent `snmpd` (`net-snmp`), already operates on the server, configure transmission of SNMP requests through the Dr.Web MIB branch from `snmpd` to Dr.Web SNMPD. For that purpose, edit the `snmpd` configuration file (usually for GNU/Linux the file is as follows: `/etc/snmp/snmpd.conf`), by adding the following line in it:

```
proxy -v <version> -c <community> <address>:<port> <MIB branch>
```

Where:

- `<version>`—SNMP version in use (2c, 3).
- `<community>`—"community string" used by Dr.Web SNMPD.
- `<address>:<port>`—network socket which is listened by Dr.Web SNMPD.
- `<MIB branch>`—OID of the MIB branch containing [descriptions](#) of variables and SNMP notifications (*trap*) used by Dr.Web (the OID equals `.1.3.6.1.4.1.29690`).

If you are using the default settings of Dr.Web SNMP agent, then the added line should look like this:

```
proxy -v 2c -c public localhost:50000 .1.3.6.1.4.1.29690
```

Note that since port 161 in this case will be used by the system standard `snmpd`, it is required to specify another port for Dr.Web SNMPD in the `ListenAddress` [parameter](#) (in this example, 50000).

## Command-Line Arguments

To launch Dr.Web SNMPD from the command line of the operating system, the following command is used:

```
$ <opt_dir>/bin/drweb-snmpd [<parameters>]
```

Dr.Web SNMPD can process the following options:

Parameter	Description
<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion.



	<b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.

**Example:**

```
$ /opt/drweb.com/bin/drweb-snmpd --help
```

This command outputs short help information on Dr.Web SNMPD.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon when needed (as a rule, at the startup of the operating system). To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-snmpd`.

## Configuration Parameters

The component uses configuration parameters which can be found in the [SNMPD] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

The section contains the following parameters:

Parameter	Description
LogLevel <i>{logging level}</i>	<a href="#">Logging level</a> of the component.  If the parameter value is not specified, the DefaultLogLevel parameter value from the [Root] <a href="#">section</a> is used.  Default value: Notice
Log <i>{log type}</i>	<a href="#">Logging method</a> of the component.  Default value: Auto
ExePath	Path to the executable file of the component.



Parameter	Description
<i>{path to file}</i>	<p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-snmppd</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-snmppd</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-snmppd</code></li></ul>
<code>Start</code> <i>{Boolean}</i>	<p>Launch/do not launch the component by the <a href="#">Dr.Web ConfigD</a> configuration daemon.</p> <p>When you specify the <code>Yes</code> value for this parameter, it the configuration daemon will start the component immediately; and when you specify the <code>No</code> value, the configuration daemon will terminate the component immediately.</p> <p>Default value: <code>No</code></p>
<code>RunAsUser</code> <i>{UID   user name}</i>	<p>The user on whose behalf the component should be run. The user name can be specified either as the user's number UID or as the user's login. If the user name consists of numbers (i.e. similar to number UID), it is specified with the "name:" prefix, for example: <code>RunAsUser = name:123456</code>.</p> <p>When a user name is not specified, the component operation terminates with an error after the startup.</p> <p>Default value: <code>drweb</code></p>
<code>ListenAddress</code> <i>{address}</i>	<p>Address (IP address and port) listened by Dr.Web SNMPD, which is waiting for client connections (SNMP managers).</p> <p>Note that interaction with <code>snmpd</code> requires a specified port, different from the standard port (161), and <code>snmpd</code> must be <a href="#">configured</a> for proxying.</p> <p>Default value: <code>127.0.0.1:161</code></p>
<code>SnmpVersion</code> <i>{V2c   V3}</i>	<p>The current version of SNMP protocol (<i>SNMPv2c</i> or <i>SNMPv3</i>).</p> <p>Default value: <code>V2c</code></p>
<code>V3EngineId</code> <i>{string}</i>	<p>Identifier (string) of <i>Engine ID</i> for <i>SNMPv3</i> (according to <a href="#">RFC 3411</a>).</p> <p>Default value: <code>800073FA044452574542</code></p>
<code>TrapReceiver</code> <i>{address list}</i>	<p>List of addresses (IP address and port) where Dr.Web SNMPD sends <i>SNMP trap</i> notifications after Dr.Web Industrial for UNIX File Servers components detected a threat.</p> <p>You can specify a list as the parameter value. The values in the list must be separated with commas (each value in the</p>





Parameter	Description
	<p>quotation marks). The parameter can be specified more than once in the section (in this case, all its values are combined into one list).</p> <p>Example: Add sockets 192.168.0.1:1234 and 10.20.30.45:5678 to the list.</p> <ol style="list-style-type: none"><li>Adding of values to the configuration file.<ul style="list-style-type: none"><li>Two values in one string:<div><pre>Section [SNMPD] TrapReceiver = "192.168.0.1:1234", "10.20.30.45:5678"</pre></div></li><li>Two strings (one value per a string):<div><pre>[SNMPD] TrapReceiver = 192.168.0.1:1234 TrapReceiver = 10.20.30.45:5678</pre></div></li></ul></li><li>Adding values with the <code>drweb-ctl cfset</code> <a href="#">command</a>:<div><pre># drweb-ctl cfset SNMPD.TrapReceiver -a 192.168.0.1:1234 # drweb-ctl cfset SNMPD.TrapReceiver -a 10.20.30.45:5678</pre></div></li></ol> <p>Default value: <i>(not set)</i></p>
V2cCommunity {string}	<p>The string "SNMP read community" for authentication of SNMP managers (<i>SNMPv2c</i> protocol) when Dr.Web <a href="#">MIB variables</a> are accessed for reading.</p> <p>The parameter is used if <code>SnmpVersion = V2c</code>.</p> <p>Default value: <code>public</code></p>
V3UserName {string}	<p>The user name for authentication of SNMP managers (<i>SNMPv3</i> protocol) when Dr.Web <a href="#">MIB variables</a> are accessed for reading.</p> <p>The parameter is used if <code>SnmpVersion = V3</code>.</p> <p>Default value: <code>noAuthUser</code></p>
V3Auth {SHA(<pwd>)   MD5(<pwd>)   None}	<p>Method to authenticate SNMP managers (<i>SNMPv3</i> protocol) when Dr.Web <a href="#">MIB variables</a> are accessed for reading.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li><code>SHA (&lt;PWD&gt;)</code> —SHA hash of the password is used (&lt;PWD&gt; strings);</li></ul>



Parameter	Description
	<ul style="list-style-type: none"><li>MD5 (&lt;PWD&gt;) —MD5 hash of the password is used (&lt;PWD&gt; strings);</li><li>None—authentication is disabled.</li></ul> <p>where &lt;PWD&gt; is a plain text password.</p> <p>When specifying the parameter value from the command line, you may need to escape the brackets by using the slash mark \ in some shells.</p> <p>Examples:</p> <ol style="list-style-type: none"><li>Parameter value in the configuration file: <code>V3Auth = MD5(123456)</code></li><li>Specifying the same parameter value from the command line with the <code>drweb-ctl cfset</code> <a href="#">command</a>: <code>drweb-ctl cfset SNMPD.V3Auth MD5\ (123456\)</code></li></ol> <p>The parameter is used if <code>SnmpVersion = V3</code>.</p> <p>Default value: None</p>
V3Privacy {DES(<secret>)   AES128(<secret>)   None}	<p>Encryption method for SNMP messages (<i>SNMPv3</i> protocol).</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>DES (&lt;secret&gt;) —DES encryption algorithm;</li><li>AES128 (&lt;secret&gt;) —AES128 encryption algorithm;</li><li>None—SNMP-messages are not encrypted.</li></ul> <p>where &lt;secret&gt; is a secret key shared by the manager and the agent (<i>plain text</i>).</p> <p>When specifying the parameter value from the command line, you can need to escape the brackets by using the slash mark \ in some shells.</p> <p>Examples:</p> <ol style="list-style-type: none"><li>Parameter value in the configuration file: <code>V3Privacy = AES128(supersecret)</code></li><li>Specifying the same parameter value from the command line with the <code>drweb-ctl cfset</code> <a href="#">command</a>: <code>drweb-ctl cfset SNMPD.V3Privacy AES128\ (supersecret\)</code></li></ol> <p>The parameter is used if <code>SnmpVersion = V3</code>.</p> <p>Default value: None</p>



## Integration with SNMP Monitoring Systems

Dr.Web SNMP agent can act as data provider for any monitoring system that uses the SNMP protocol, versions 2c or 3. The list of data that is available for control and the data structure are [described](#) in the Dr.Web MIB description file `DRWEB-SNMPD-MIB.txt` supplied together with Dr.Web Industrial for UNIX File Servers. This file is located in the directory `<opt_dir>/share/drweb-snmpd/mibs`.

For easy configuration, the component is supplied with templates of settings for popular monitoring systems:

- [Munin](#)
- [Nagios](#)
- [Zabbix](#)

Customization templates for monitoring systems are located in the `<opt_dir>/share/drweb-snmpd/connectors` directory.

## Integration with Munin Monitoring System

The Munin monitoring system includes the central server (master) munin, which collects statistics from clients munin-node residing locally on the monitored hosts. At request of the server, each monitoring client collects data about monitored host operation by starting *plug-ins* (*plug-ins*) that provide data transferred to the server.

To enable connection between Dr.Web SNMPD and the Munin monitoring system, a ready-to-use plug-in Dr.Web used by munin-node is supplied. The plug-in resides in the `<opt_dir>/share/drweb-snmpd/connectors/munin/plugins` directory. This plug-in collects data required for construction of the following two graphs:

- Number of detected threats.
- File scan statistics.

These plug-ins support SNMP protocols versions 1, 2c and 3. Based on these template plug-ins, you can create any other plug-ins to poll the status of Dr.Web Industrial for UNIX File Servers components via Dr.Web SNMPD.

In the `<opt_dir>/share/drweb-snmpd/connectors/munin` directory, the following files are located.

File	Description
<code>plugins/snmp__drweb_malware</code>	The munin-node plug-in for polling Dr.Web SNMPD via SNMP to gather the number of threats detected by Dr.Web Industrial for UNIX File Servers on the host.



File	Description
plugins/snmp__drweb_filecheck	The munin-node plug-in for polling Dr.Web SNMPD via SNMP to gather the statistics of files scanned by Dr.Web Industrial for UNIX File Servers on the host.
plugin-conf.d/drweb.cfg	An example of the munin-node configuration for the environment variables of the Dr.Web plug-ins.

## Connecting a host to Munin

In the present instruction, it is assumed that the Munin monitoring system is already deployed on the monitoring server and the monitored host features an installed and functioning Dr.Web SNMPD (it is possible for the component to function in [proxy](#) mode together with `snmpd`) and `munin-node`.

### 1. Monitored host configuration

- Copy the `snmp__drweb_*` files to the directory with plug-in libraries `munin-node` (the directory depends on the OS). For example, in Debian/Ubuntu operating systems, the path is `/usr/share/munin/plugins`.
- Configure `munin-node` by connecting to it the supplied Dr.Web plug-ins. To do this, use the `munin-node-configure` utility that is distributed with `munin-node`.

For example, the following command:

```
$ munin-node-configure --shell --snmp localhost
```

will display on a terminal screen a list of commands for creation of required symbolic links to plug-ins. Copy and execute them in the command line. Note that the specified command presumes that:

- 1) `munin-node` is installed at the same host where Dr.Web SNMPD is installed. If it is not the case, please specify the correct FQDN or an IP address of the monitored host instead of a `localhost` value;
  - 2) Dr.Web SNMPD uses SNMP version 2c. If it is not the case, specify the correct SNMP version in `munin-node-configure` command. The command has several arguments for flexible configuration of plug-ins, e.g., you can specify the SNMP protocol version, port that is listened by SNMP agent at the monitored host, an actual value of the *community string*, and so on. If required, refer to the manual on `munin-node-configure` command.
- If necessary, define (or redefine) parameter values of the environment, where installed Dr.Web plug-ins for `munin-node` must be executed. As the environment parameters, the value *community string* is used. It is the port utilized by the SNMP agent, and so on. These parameters must be defined in the file `/etc/munin/plugin-conf.d/drweb` (create it if required). As an example of this file, use the supplied file `drweb.cfg`.



- In the munin-node configuration file (`munin-node.conf`), specify a regular expression to include all IP addresses of hosts that are allowed to connect munin servers (masters) to munin-node for receiving the values of the monitored parameters, for example:

```
allow ^10\.20\.30\.40$
```

In this case, only the IP address `10.20.30.40` is allowed to receive host parameters.

- Restart munin-node, for example, by using the following command:

```
# service munin-node restart
```

## 2. Munin server (master) configuration

Add the address and identifier of the monitored host to the Munin configuration file `munin.conf`, which is located, by default, in `/etc` directory (in Debian/Ubuntu operating systems it is `/etc/munin/munin.conf`):

```
[<ID>; <hostname> . <domain>]  
address <host IP address>  
use_node_name yes
```

where `<ID>` is the displayed host identifier, `<hostname>` is the name of the host, `<domain>` is the name of the domain, `<host IP address>` is the IP address of the host.

For official documentation on configuration of the Munin monitoring system, refer to <http://guide.munin-monitoring.org/en/latest>.

## Integration with Zabbix Monitoring System

File templates, required for establishing connection between Dr.Web SNMPD and the Zabbix monitoring system, are located in the `<opt_dir>/share/drweb-snmptt/connectors/zabbix` directory.

File	Description
<code>zbx_drweb.xml</code>	Template for description of the monitored host that features installed Dr.Web Industrial for UNIX File Servers
<code>snmptt.drweb.zabbix.conf</code>	Configuring the <code>snmptt</code> utility—which is an <i>SNMP trap</i> handler

Template for description of the monitored host features:

- Description of counters ("*items*", according to the terminology of Zabbix). By default, the template is set to be used with SNMP v2.
- The set of predefined graphs: number of scanned files and distribution of detected threats by their type.



## Connecting a host to Zabbix

In the present instruction, it is assumed that the Zabbix monitoring system is already deployed on the monitoring server and the monitored host features an installed and functioning Dr.Web SNMPD (it is possible for the component to function in [proxy](#) mode together with `snmpd`). Moreover, if you want to receive *SNMP trap* notifications from the monitored host (including notification on threats detected by Dr.Web Industrial for UNIX File Servers on a protected server), install the `net-snmp` package on the monitoring server (standard tools `snmptt` and `snmptrapd` are used).

1. In the Zabbix web interface, on the **Configuration** → **Templates** tab import the template of the monitored host from the `<opt_dir>/share/drweb-snmppd/connectors/zabbix/zbx_drweb.xml` file.
2. Add the monitored host to the appropriate list (at **Hosts** → **Create host**). Specify correct parameters of the host and settings of the SNMP interface (they must match the settings of `drweb-snmppd` and `snmpd` on the host):

- The **Host** tab:

**Host name:** *drweb-host*

**Visible name:** *DRWEB\_HOST*

**Groups:** select *Linux servers*

**Snmp interfaces:** Click **Add** specify the IP address and port are used by Dr.Web SNMPD (it is considered that Dr.Web SNMPD operates on the local host, so the address *127.0.0.1* and the port *161* are specified by default).

- The **Templates** tab:

Press **Add**, check *DRWEB*, press **Select**.

- The **Macros** tab:

**Macro:** `{ $SNMP_COMMUNITY }`

**Value:** specify "read community" for SNMP V2c (by default, *public*).

Click **Save**.

Note: The `{ $SNMP_COMMUNITY }` macro can be specified directly in the host template.



By default, the imported *DRWEB* template is configured for SNMP v2. If you need to use another version of SNMP, edit the template accordingly on the appropriate page.

3. After the template is bound to the monitored host, if SNMP settings are specified correctly, the Zabbix monitoring system will start to collect data for counters (*items*) of the template; the collected data will be displayed on the **Monitoring** → **Latest Data** and **Monitoring** → **Graphs**.
4. A special *item drweb-traps* is used for collecting *SNMP trap* notifications from Dr.Web SNMPD. The log pf received *SNMP trap* notifications is available on the **Monitoring** → **Latest Data** → **drweb-traps** → **history** page. To collect notifications, Zabbix uses standard



tools `snmptt` and `snmptrapd` from the `net-snmp` package. For details on how to configure the tools for receiving *SNMP trap* notifications from Dr.Web SNMPD, see below.

5. If necessary, you can configure a trigger that will change its state upon receiving an *SNMP trap* notification from Dr.Web SNMPD. Changing of its state can be used as an event source for generation appropriate notifications. The example below shows an expression for configuration of a trigger; the expression is specified in the **trigger expression** field:

- For Zabbix versions 2.x:

```
{TRIGGER.VALUE}=0 &
{DRWEB:snmptrap[.*\1\3\6\1\4\1\29690\..*].nodata(60)}=1 ) |
{TRIGGER.VALUE}=1 &
{DRWEB:snmptrap[.*\1\3\6\1\4\1\29690\..*].nodata(60)}=0)
```

- For Zabbix versions 3.x:

```
{TRIGGER.VALUE}=0 and {drweb-host:snmptrap[".29690."].nodata(60)}=1 ) or
{TRIGGER.VALUE}=1 and {drweb-host:snmptrap[".29690."].nodata(60)}=0 )
```

An event is triggered (the value is set to 1) if the log of *SNMP trap* notifications from Dr.Web SNMPD was updated within a minute. If the log was not updated within the next minute, the value of the trigger is set to 0 again.

In **Severity**, for this trigger it is recommended that notification type is different from *Not classified*, for example, *Warning*.

## Configuring Receipt of SNMP trap notifications for Zabbix

1. On the monitored host, in Dr.Web SNMPD settings (the `TrapReceiver` parameter), you should specify an address to be listened by `snmptrapd` on the host where Zabbix operates, for example:

```
SNMPD.TrapReceiver = 10.20.30.40:162
```

2. In the configuration file of `snmptrapd` (`snmptrapd.conf`), specify the same address and an application for processing received *SNMP trap* notifications (in this example, `snmpthandler`, `snmptt` component):

```
snmpTrapdAddr 10.20.30.40:162
traphandle default /usr/sbin/snmptthandler
```

Add the following string to the file, so that `snmptt` does not discard *SNMP trap* sent by Dr.Web SNMPD as unknown:

```
outputOption n
```

3. The `snmptthandler` component saves received *SNMP trap* notifications to the file on the disk in accordance with the specified format, which corresponds to the regular expression set in the host template for Zabbix (the *item drweb-traps* element). The *SNMP trap* format of the saved notification is specified in the `<opt_dir>/share/drweb-`



snmpd/connectors/zabbix/snmpptt.drweb.zabbix.conf. file. The file must be copied to /etc/snmp.

- Moreover, the path to the format files must be specified in the snmpptt.ini:

```
[TrapFiles]
# A list of snmpptt.conf files (this is NOT the snmptrapd.conf file).
# The COMPLETE path and filename. Ex: '/etc/snmp/snmpptt.conf'
snmpptt_conf_files = <<END
/etc/snmp/snmpptt.conf
/etc/snmp/snmpptt.drweb.zabbix.conf
END
```

After that, restart snmpptt if it was started in daemon mode.

- In the configuration file of the Zabbix server (zabbix-server.conf), specify (or check if they are already specified) the following settings:

```
SNMPTrapperFile=/var/log/snmpptt/snmpptt.log
StartSNMPTrapper=1
```

where /var/log/snmpptt/snmpptt.log is a log file used by snmpptt to register information on received SNMP trap notifications.

For official documentation on Zabbix, refer to <https://www.zabbix.com/documentation/current/en>.

## Integration with Nagios Monitoring System

Files with Nagios configuration examples, required for establishing connection between Dr.Web SNMPD and the Nagios monitoring system, are located in the <opt\_dir>/share/drweb-snmpd/connectors/nagios directory.

File	Description
nagiosgraph/rrdopts.conf-sample	Example of the RRD configuration file
objects/drweb.cfg	Configuration file describing <i>drweb</i> objects
objects/nagiosgraph.cfg	The configuration file of the component for graph plotting used by Nagiosgraph used by Nagios
plugins/check_drweb	The script for collecting data from the host on which Dr.Web Industrial for UNIX File Servers is installed
plugins/eventhandlers/submit_check_result	The script for handling <i>SNMP trap</i> notifications
snmp/snmpptt.drweb.nagios.conf	Configuring the snmpptt utility—which is an <i>SNMP trap</i> handler





## Connecting a host to Nagios

In the present instruction, it is assumed that the Nagios monitoring system is already deployed on the monitoring server, including configuration of the web server and the graphical tool Nagiosgraph, and the monitored host features an installed and functioning Dr.Web SNMPD (it is possible for the component to function in [proxy](#) mode together with `snmpd`). Moreover, if you want to receive *SNMP trap* notifications from the monitored host (including notification on threats detected by Dr.Web Industrial for UNIX File Servers on a protected server), install the `net-snmp` package on the monitoring server (standard tools `snmptt` and `snmptrapd` are used).

In the current manual, the following path conventions are used (real paths depend on the operating system and Nagios installation):

- `<NAGIOS_PLUGINS_DIR>`—directory with Nagiosplug-ins, for example: `/usr/lib64/nagios/plugins`.
- `<NAGIOS_ETC_DIR>`—directory with Nagios settings, for example: `/etc/nagios`.
- `<NAGIOS_OBJECTS_DIR>`—directory with Nagios objects, for example: `/etc/nagios/objects`.
- `<NAGIOSGRAPH_DIR>`—Nagiosgraph directory, for example: `/usr/local/nagiosgraph`.
- `<NAGIOS_PERFDATA_LOG>`—file where Nagios records results of service check (must be the same as the `perflog` file from `<NAGIOSGRAPH_DIR>/etc/nagiosgraph.conf`). Records from this file are read by the `<NAGIOSGRAPH_DIR>/bin/insert.pl` script and are recorded to the corresponding RRA archives RRD Tool.

Configuring Nagios:

1. Copy the `check_drweb` file to the `<NAGIOS_PLUGINS_DIR>` directory and the `drweb.cfg` file to the `<NAGIOS_OBJECTS_DIR>` directory.
2. Add hosts with Dr.Web Industrial for UNIX File Servers that are to be monitored to the *drweb* group. On the hosts Dr.Web SNMPD must be running. By default, only *localhost* is added to this group.
3. If required, edit the `check_drweb` command which contains instruction to contact Dr.Web SNMPD on *drweb* hosts via the `snmplwalk` tool:

```
snmpwalk -c public -v 2c $HOSTADDRESS$:161
```

specify the correct version of SNMP protocol and parameters (such as “*community string*” or authentication parameters) as well as the port. The `$HOSTADDRESS$` variable must be included in the command (as this variable is later automatically substituted by Nagios to the correct host address when the command is invoked). OID is not required in the command. It is also recommended that you specify the command together with the full path to the executable file (usually `/usr/local/bin/snmpwalk`).

4. Connect *DrWeb* objects in the `<NAGIOS_ETC_DIR>/nagios.cfg` configuration file by adding the following string to the file:



```
cfg_file=<NAGIOS_OBJECTS_DIR>/drweb.cfg
```

5. Add RRD Tool settings for *DrWeb* graphics from the `rrdopts.conf-sample` file to the `<NAGIOSGRAPH_DIR>/etc/rrdopts.conf` file.
6. If Nagiosgraph is yet to be configured, do the following steps for its configuration:
  - Copy the `nagiosgraph.cfg` file to the `<NAGIOS_OBJECTS_DIR>` directory and edit the path to the `insert.pl` script in the `process-service-perfdata-for-nagiosgraph` command; for example, as follows:

```
$ awk '$1 == "command_line" { $2 = "<NAGIOSGRAPH_DIR>/bin/insert.pl" }  
{ print }' ./objects/nagiosgraph.cfg > <NAGIOS_OBJECTS_DIR>/nagiosgraph.cfg
```

- Connect this file in the `<NAGIOS_ETC_DIR>/nagios.cfg` configuration file by adding the following line to it:

```
cfg_file=<NAGIOS_OBJECTS_DIR>/nagiosgraph.cfg
```

7. Check values of Nagios parameters in the `<NAGIOS_ETC_DIR>/nagios.cfg` configuration file:

```
check_external_commands=1  
execute_host_checks=1  
accept_passive_host_checks=1  
enable_notifications=1  
enable_event_handlers=1  
  
process_performance_data=1  
service_perfdata_file=/usr/nagiosgraph/var/rrd/perfdata.log  
service_perfdata_file_template=$LASTSERVICECHECK$||$HOSTNAME$||$SERVICEDESC$||$SERVICEOUTPUT$||$SERVICEPERFDATA$  
service_perfdata_file_mode=a  
service_perfdata_file_processing_interval=30  
service_perfdata_file_processing_command=process-service-perfdata-for-nagiosgraph  
  
check_service_freshness=1  
enable_flap_detection=1  
enable_embedded_perl=1  
enable_environment_macros=1
```

## Configuring Receipt of SNMP trap notifications for Nagios

1. On the monitored host in Dr.Web SNMPD settings (the `TrapReceiver` parameter), specify an address to be listened by `snmptrapd` on the host where Nagios operates, for example:

```
SNMPD.TrapReceiver = 10.20.30.40:162
```

2. Check for existing the `<NAGIOS_PLUGINS_DIR>/eventhandlers/submit_check_result` script which will be invoked when *SNMP trap* is received. If the script is missing, copy the



- submit\_check\_result file to this location from the `<opt_dir>/share/drweb-snmpd/connectors/nagios/plugins/eventhandlers/` directory. In this file, change the path specified in the `CommandFile` parameter. It must have the same value as the `command_file` parameter in the `<NAGIOS_ETC_DIR>/nagios.cfg` file.
3. Copy the `snmptt.drweb.nagios.conf` file to the `/etc/snmp/snmp/` directory. In this file, change the path to the `submit_check_result`—for example, by using the following command:

```
$ awk '$1 == "EXEC" { $2 =  
<NAGIOS_PLUGINS_DIR>/eventhandlers/submit_check_result }{ print }'  
./snmp/snmptt.drweb.nagios.conf > /etc/snmp/snmp/snmptt.drweb.nagios.conf
```

4. Add the `" /etc/snmp/snmptt.drweb.nagios.conf"` string to the `/etc/snmp/snmptt.ini` file. After that, restart `snmptt` if it was started in daemon mode.

After all required configuration files of Nagios are added and edited, run Nagios in debug mode by using the following command:

```
# nagios -v <NAGIOS_ETC_DIR>/nagios.cfg
```

Upon receipt of this command, Nagios will check for configuration errors. If no error is found, Nagios can be restarted as usual (for example, by using the `service nagios restart` command).

For official documentation on Nagios, refer to <https://www.nagios.org/documentation>.

## Dr.Web SNMP MIB

The list of operating parameters of Dr.Web Industrial for UNIX File Servers that can be fetched by external monitoring systems via the SNMP protocol is provided in the table below.

Parameter name	OID parameter	Type and description of the parameter
Common prefix for all names: <code>.iso.org.dod.internet.private.enterprises.drweb.drwebSnmpd</code> Common OID prefix for all names: <code>.1.3.6.1.4.1.29690.2</code>		
<b>alert</b>	<b>Asynchronous notifications about events (SNMP traps)</b>	
<i>threatAlert</i>	<code>.1.1</code>	Notification about a detected threat
<code>threatAlertFile</code>	<code>.1.1.1</code>	Name of the infected file (string)
<code>threatAlertType</code>	<code>.1.1.2</code>	Threat type (integer *)



Parameter name	OID parameter	Type and description of the parameter
threatAlertName	.1.1.3	Name of the threat (string)
threatAlertOrigin	.1.1.4	Identifier of the component that detected the threat (integer***)
threatAlertRemoteIp	.1.1.5	IP address of the remote host that was used to access the file (string)
threatAlertRemoteUser	.1.1.6	Name of the remote user who accessed the file (string)
threatAlertRemoteDomain	.1.1.7	IP address of the remote host (FQDN) that was used to access the file (string)
<i>threatActionErrorAlert</i>	.1.2	Notification about an error which occurred when trying to neutralize the threat
threatActionErrorAlertFile	.1.2.1	Name of the infected file (string)
threatActionErrorAlertType	.1.2.2	Threat type (integer *)
threatActionErrorAlertName	.1.2.3	Name of the threat (string)
threatActionErrorAlertOrigin	.1.2.4	Identifier of the component that detected the threat (integer***)
threatActionErrorAlertError	.1.2.5	Description of an error (string)
threatActionErrorAlertErrorCode	.1.2.6	Last exit code (an integer corresponding to codes from the error catalog)
threatActionErrorAlertAction	.1.2.7	Failed action (integer: 1—cure; 2—quarantine; 3—delete; 4—report; 5—ignore)
<i>componentFailureAlert</i>	.1.3	Notification about a component failure
componentFailureAlertName	.1.3.1	Component identifier (integer***)
componentFailureAlertExitCodeDescription	.1.3.2	Component exit code description (string)
componentFailureAlertExitCode	.1.3.3	Last exit code (an integer corresponding to codes from the error catalog)



Parameter name	OID parameter	Type and description of the parameter
<i>infectedUrlAlert</i>	.1.4	Notification about blocking a malicious URL (for HTTP/HTTPS connections)
infectedUrlAlertUrl	.1.4.1	The URL that was blocked (string)
infectedUrlAlertDirection	.1.4.2	HTTP message direction (integer: 1—request, 2—response)
infectedUrlAlertType	.1.4.3	Threat type (integer *)
infectedUrlAlertName	.1.4.4	Name of the threat (string)
infectedUrlAlertOrigin	.1.4.5	Identifier of the component that detected the threat (integer***)
infectedUrlAlertSrcIp	.1.4.6	IP address of a connection source (string)
infectedUrlAlertSrcPort	.1.4.7	Port of the connection source (integer)
infectedUrlAlertDstIp	.1.4.8	IP address of a connection destination point (string)
infectedUrlAlertDstPort	.1.4.9	Port of the connection destination point (integer)
infectedUrlAlertSniHost	.1.4.10	SNI of the connection destination point (for SSL connections) (string)
infectedUrlAlertExePath	.1.4.11	Executable path of the program that established the connection (string)
infectedUrlAlertUserName	.1.4.12	Name of the user as whom the program establishing the connection is running (string)
<i>categoryUrlAlert</i>	.1.6	Notification about blocking a URL belonging to the unwanted category
categoryUrlAlertUrl	.1.6.1	The URL that was blocked (string)
categoryUrlAlertCategory	.1.6.2	Web resource category to which the URL belongs (integer**)



Parameter name	OID parameter	Type and description of the parameter
categoryUrlAlertOrigin	.1.6.3	Identifier of the component that detected the threat (integer***)
categoryUrlAlertSrcIp	.1.6.4	IP address of a connection source (string)
categoryUrlAlertSrcPort	.1.6.5	Port of the connection source (integer)
categoryUrlAlertDstIp	.1.6.6	IP address of a connection destination point (string)
categoryUrlAlertDstPort	.1.6.7	Port of the connection destination point (integer)
categoryUrlAlertSniHost	.1.6.8	SNI of the connection destination point (for SSL connections) (string)
categoryUrlAlertExePath	.1.6.9	Executable path of the program that established the connection (string)
categoryUrlAlertUserName	.1.6.10	Name of the user as whom the program establishing the connection is running (string)
expiringLicenseAlert	.1.10	Days before license expiration (integer)
outdatedBasesAlert	.1.11	Timestamp of the last successful attempt of updating databases (UNIX time)
<b>stat</b>	<b>Statistics on the operation of Dr.Web Industrial for UNIX File Servers</b>	
<i>threatCounters</i>	.2.1	Counters of detected threats
knownVirus	.2.1.1	Number of detected known viruses (counter; integer)
suspicious	.2.1.2	Number of detected suspicious objects (counter; integer)
adware	.2.1.3	Number of detected adware (counter; integer)
dialers	.2.1.4	Number of detected dialers (counter; integer)



Parameter name	OID parameter	Type and description of the parameter
joke	.2.1.5	Number of detected joke programs (counter; integer)
riskware	.2.1.6	Number of detected riskware (counter; integer)
hacktool	.2.1.7	Number of detected hacktools (counter; integer)
<i>scanErrors</i>	.2.2	Counters of the errors that occurred while files were scanned
sePathNotAbsolute	.2.2.1	Number of occurrences of the "Path is not absolute" error (counter; integer)
seFileNotFound	.2.2.2	Number of occurrences of the "File not found" error (counter; integer)
seFileNotRegular	.2.2.3	Number of occurrences of the "File is not a regular file" error (counter; integer)
seFileNotBlockDevice	.2.2.4	Number of occurrences of the "File is not a block device" error (counter; integer)
seNameTooLong	.2.2.5	Number of occurrences of the "Path or file name is too long" error (counter; integer)
seNoAccess	.2.2.6	Number of occurrences of the "Permission denied" error (counter; integer)
seReadError	.2.2.7	Number of occurrences of "Read error" (counter; integer)
seWriteError	.2.2.8	Number of occurrences of "Write error" (counter; integer)
seFileTooLarge	.2.2.9	Number of occurrences of the "File size too big" error (counter; integer)
seFileBusy	.2.2.10	Number of occurrences of the "File is busy" error (counter; integer)



Parameter name	OID parameter	Type and description of the parameter
seUnpackingError	.2.2.20	Number of occurrences of "Unpacking error" (counter; integer)
sePasswordProtectetd	.2.2.21	Number of occurrences of the "Password protected" error (counter; integer)
seArchCrcError	.2.2.22	Number of occurrences of "Archive Cyclic Redundancy Check error" (counter; integer)
seArchInvalidHeader	.2.2.23	Number of occurrences of the "Invalid archive header" error (counter; integer)
seArchNoMemory	.2.2.24	Number of occurrences of the "Not enough memory to process archive" error (counter; integer)
seArchIncomplete	.2.2.25	Number of occurrences of the "Incomplete archive" error (counter; integer)
seCanNotBeCured	.2.2.26	Number of occurrences of the "Object cannot be cured" error (counter; integer)
sePackerLevelLimit	.2.2.30	Number of occurrences of the "Packer nesting level limit reached" error (counter; integer)
seArchiveLevelLimit	.2.2.31	Number of occurrences of the "Archive nesting level limit reached" error (counter; integer)
seMailLevelLimit	.2.2.32	Number of occurrences of the "Mail nesting level limit reached" error (counter; integer)
seContainerLevelLimit	.2.2.33	Number of occurrences of the "Container nesting level limit reached" error (counter; integer)
seCompressionLimit	.2.2.34	Number of occurrences of the "Compression rate limit reached" error (counter; integer)
seReportSizeLimit	.2.2.35	Number of occurrences of the "Report size limit reached" error





Parameter name	OID parameter	Type and description of the parameter
		(counter; integer)
seScanTimeout	.2.2.40	Number of occurrences of the "Scan timeout expired" error (counter; integer)
seEngineCrash	.2.2.41	Number of occurrences of the "Engine crash detected" error (counter; integer)
seEngineHangup	.2.2.42	Number of occurrences of the "Engine hang-up detected" error (counter; integer)
seEngineError	.2.2.44	Number of occurrences of "Engine internal error" (counter; integer)
seNoLicense	.2.2.45	Number of occurrences of the "No valid license" error (counter; integer)
seCuringLimitReached	.2.2.47	Number of occurrences of the "Curing limit reached" error (counter; integer)
seNonSupportedDisk	.2.2.50	Number of occurrences of the "Unsupported disk" error (counter; integer)
seUnexpectedError	.2.2.100	Number of occurrences of the "Unexpected error" (counter; integer)
scanLoadAverage	.2.3	Metrics of the file scanning load
filesScannedTable	.2.3.1	Average numbers of files scanned at the request of other components
filesScannedEntry	.2.3.1.1	Component (table row; record)
filesScannedIndex	.2.3.1.1.1	Index of the component (identifier; integer***)
filesScannedOrigin	.2.3.1.1.2	Name of the component
filesScannedlmin	.2.3.1.1.3	Average (for a minute) number of files scanned per second (string)



Parameter name	OID parameter	Type and description of the parameter
filesScanned5min	.2.3.1.1.4	Average (for 5 minutes) number of files scanned per second (string)
filesScanned15min	.2.3.1.1.5	Average (for 15 minutes) number of files scanned per second (string)
<i>bytesScannedTable</i>	.2.3.2	Average speed (in bytes) of scanning performed at the request of other components
bytesScannedEntry	.2.3.2.1	Component (table row; record)
bytesScannedIndex	.2.3.2.1.1	Index of the component (identifier; integer***)
bytesScannedOrigin	.2.3.2.1.2	Name of the component
bytesScanned1min	.2.3.2.1.3	Average (for a minute) number of bytes scanned per second (string)
bytesScanned5min	.2.3.2.1.4	Average (for 5 minutes) number of bytes scanned per second (string)
bytesScanned15min	.2.3.2.1.5	Average (for 15 minutes) number of bytes scanned per second (string)
<i>cacheHitFilesTable</i>	.2.3.3	Cache usage for scanned files at the request of the components
cacheHitFilesEntry	.2.3.3.1	Component (table row; record)
cacheHitFilesIndex	.2.3.3.1.1	Index of the component (identifier; integer***)
cacheHitFilesOrigin	.2.3.3.1.2	Name of the component
cacheHitFiles1min	.2.3.3.1.3	The average (for a minute) number of reports retrieved from the cache per second (string)
cacheHitFiles5min	.2.3.3.1.4	Average (for 5 minutes) number of reports retrieved from cache per second (string)
cacheHitFiles15min	.2.3.3.1.5	Average (for 15 minutes) number of reports retrieved from cache



Parameter name	OID parameter	Type and description of the parameter
		per second (string)
<i>errorsTable</i>	.2.3.4	Number of errors during scanning performed at the request of the components
errorsEntry	.2.3.4.1	Component (table row; record)
errorsIndex	.2.3.4.1.1	Index of the component (identifier; integer***)
errorsOrigin	.2.3.4.1.2	Name of the component
errors1min	.2.3.4.1.3	Average (for a minute) number of scanning errors per second (string)
errors5min	.2.3.4.1.4	Average (for 5 minutes) number of scanning errors per second (string)
errors15min	.2.3.4.1.5	Average (for 15 minutes) number of scanning errors per second (string)
<b>info</b>	<b>Information about the current state of Dr.Web Industrial for UNIX File Servers</b>	
<i>components</i>	.3.1	Status of Dr.Web Industrial for UNIX File Servers Components
<i>configd</i>	.3.1.1	drweb-configd component data
configdState	.3.1.1.1	Component status (integer****)
configdExitCode	.3.1.1.2	Last exit code (an integer corresponding to codes from the error catalog)
configdExitTime	.3.1.1.3	Termination time ( <i>UNIX time</i> )
<i>configdInstalledApps</i>	.3.1.1.101	List of installed components
<i>configdAppEntry</i>	.3.1.1.101.1	Information about the installed component (table row; record)
configdAppIndex	.3.1.1.101.1.1	Index (number) of the installed component (integer)



Parameter name	OID parameter	Type and description of the parameter
configdAppName	.3.1.1.101.1.2	Name of the installed component (string)
configdAppExePath	.3.1.1.101.1.3	Component executable path (string)
configdAppInstallTime	.3.1.1.101.1.4	Component installation time ( <i>UNIX time</i> )
configdAppIniSection	.3.1.1.101.1.5	Name of the section with the component parameters in the configuration file (string)
<i>scanEngine</i>	.3.1.2	drweb-se component data
scanEngineState	.3.1.2.1	Component status (integer****)
scanEngineExitCode	.3.1.2.2	Last exit code (an integer corresponding to codes from the error catalog)
scanEngineExitTime	.3.1.2.3	Termination time ( <i>UNIX time</i> )
scanEngineStatus	.3.1.2.101	Dr.Web Virus-Finding Engine status (integer)
scanEngineVersion	.3.1.2.102	Dr.Web Virus-Finding Engine version (string)
scanEngineVirusRecords	.3.1.2.103	Number of virus records (integer)
scanEngineMaxForks	.3.1.2.104	Maximum number of child processes for scanning (integer)
<i>scanEngineQueues</i>	.3.1.2.105	Scan task queues
<i>scanEngineQueuesLow</i>	.3.1.2.105.1	The queue of low-priority tasks
scanEngineQueueLowOut	.3.1.2.105.1.1	Number of low-priority tasks popped from the queue and passed for processing (counter; integer)
scanEngineQueueLowSize	.3.1.2.105.1.2	Number of low-priority tasks in the queue waiting to be processed (counter; integer)
<i>scanEngineQueuesMedium</i>	.3.1.2.105.2	The queue of normal-priority tasks



Parameter name	OID parameter	Type and description of the parameter
<code>scanEngineQueueMediumOut</code>	<code>.3.1.2.105.2.1</code>	Number of normal-priority tasks popped from the queue and passed for processing (counter; integer)
<code>scanEngineQueueMediumSize</code>	<code>.3.1.2.105.2.2</code>	Number of normal-priority tasks in the queue waiting to be processed (counter; integer)
<i><code>scanEngineQueuesHigh</code></i>	<code>.3.1.2.105.3</code>	Queue of high-priority tasks
<code>scanEngineQueueHighOut</code>	<code>.3.1.2.105.3.1</code>	Number of high-priority tasks popped from the queue and passed for processing (counter; integer)
<code>scanEngineQueueHighSize</code>	<code>.3.1.2.105.3.2</code>	Number of high-priority tasks in the queue waiting to be processed (counter; integer)
<i><code>scanEngineVirusBasesTable</code></i>	<code>.3.1.2.106</code>	The list of virus databases
<i><code>scanEngineVirusBasesEntry</code></i>	<code>.3.1.2.106.1</code>	Information about the virus database (table row; record)
<code>scanEngineVirusBaseIndex</code>	<code>.3.1.2.106.1.1</code>	Index of the virus database (integer)
<code>scanEngineVirusBasePath</code>	<code>.3.1.2.106.1.2</code>	Path to the virus database file (string)
<code>scanEngineVirusBaseRecords</code>	<code>.3.1.2.106.1.3</code>	Number of records in the virus database (integer)
<code>scanEngineVirusBaseVersion</code>	<code>.3.1.2.106.1.4</code>	Version of the virus database (integer)
<code>scanEngineVirusBaseTimestamp</code>	<code>.3.1.2.106.1.5</code>	Timestamp of the virus database ( <i>UNIX time</i> )
<code>scanEngineVirusBaseMD5</code>	<code>.3.1.2.106.1.6</code>	MD5 checksum (string)
<code>scanEngineVirusBaseLoadResult</code>	<code>.3.1.2.106.1.7</code>	Result of downloading the virus database (string)
<i><code>scanEngineQueuesTab</code></i>	<code>.3.1.2.107</code>	The list of scan task queues
<i><code>scanEngineQueueEntry</code></i>	<code>.3.1.2.107.1</code>	Information about the queue (table row; record)



Parameter name	OID parameter	Type and description of the parameter
scanEngineQueueIndex	.3.1.2.107.1.1	Index (number) of the queue (integer)
scanEngineQueueName	.3.1.2.107.1.2	Name of the queue (string)
scanEngineQueueOut	.3.1.2.107.1.3	Number of high-priority tasks popped from the queue and passed for processing (counter; integer)
scanEngineQueueSize	.3.1.2.107.1.4	Number of tasks in the queue waiting to be processed (counter; integer)
<i>fileCheck</i>	.3.1.3	drweb-filecheck component data
fileCheckState	.3.1.3.1	Component status (integer****)
fileCheckExitCode	.3.1.3.2	Last exit code (an integer corresponding to codes from the error catalog)
fileCheckExitTime	.3.1.3.3	Termination time ( <i>UNIX time</i> )
fileCheckScannedFiles	.3.1.3.101	Number of scanned files (counter; integer)
fileCheckScannedBytes	.3.1.3.102	Number of scanned bytes (counter; integer)
fileCheckCacheHitFiles	.3.1.3.103	Number of scan reports retrieved from the cache for scanned files (counter; integer)
fileCheckScanErrors	.3.1.3.104	Number of scanning engine errors (counter; integer)
<i>fileCheckScanStat</i>	.3.1.3.105	List of clients
<i>fileCheckClientEntry</i>	.3.1.3.105.1	Information about a client (table row; record)
fileCheckClientIndex	.3.1.3.105.1.1	Index (number) of the client (integer)
fileCheckClientName	.3.1.3.105.1.2	Name of the client component (string)



Parameter name	OID parameter	Type and description of the parameter
fileCheckClientScannedFiles	.3.1.3.105.1.3	Number of files scanned for this client (counter; integer)
fileCheckClientScannedBytes	.3.1.3.105.1.4	Number of bytes scanned for this client (counter; integer)
fileCheckClientCacheHitFiles	.3.1.3.105.1.5	Number of scan reports retrieved for this client from the cache for scanned files (counter; integer)
fileCheckClientScanErrors	.3.1.3.105.1.6	Number of scanning engine errors for this client (counter; integer)
<i>update</i>	.3.1.4	drweb-update component data
updateState	.3.1.4.1	Component status (integer****)
updateExitCode	.3.1.4.2	Last exit code (an integer corresponding to codes from the error catalog)
updateExitTime	.3.1.4.3	Termination time ( <i>UNIX time</i> )
updateBytesSent	.3.1.4.101	Number of sent bytes (counter; integer)
updateBytesReceived	.3.1.4.102	Number of received bytes (counter; integer)
<i>esagent</i>	.3.1.5	drweb-esagent component data
esagentState	.3.1.5.1	Component status (integer****)
esagentExitCode	.3.1.5.2	Last exit code (an integer corresponding to codes from the error catalog)
esagentExitTime	.3.1.5.3	Termination time ( <i>UNIX time</i> )
esagentWorkStatus	.3.1.5.101	Component operation mode (integer: 1—standalone mode, 2—connecting, 3—awaiting connection, 4—connection has been approved)
esagentIsConnected	.3.1.5.102	Connected to the server (integer: 0—no, 1—yes)



Parameter name	OID parameter	Type and description of the parameter
esagentServer	.3.1.5.103	Address of the centralized protection server in use (string)
<i>netcheck</i>	.3.1.6	drweb-netcheck component data
netcheckState	.3.1.6.1	Component status (integer****)
netcheckExitCode	.3.1.6.2	Last exit code (an integer corresponding to codes from the error catalog)
netcheckExitTime	.3.1.6.3	Termination time ( <i>UNIX time</i> )
netcheckLocalSeForks	.3.1.6.101	The number of scan engine processes available locally (integer)
netcheckRemoteSeForks	.3.1.6.102	Number of scan engine processes available remotely (integer)
netcheckLocalFilesScanned	.3.1.6.103	Number of files that have been scanned locally (counter; integer)
netcheckNetworkFilesScanned	.3.1.6.104	Number of files that have been scanned remotely (counter; integer)
netcheckLocalBytesScanned	.3.1.6.105	Number of bytes that have been scanned locally (counter; integer)
netcheckNetworkBytesScanned	.3.1.6.106	Number of bytes that have been scanned remotely (counter; integer)
netcheckLocalBytesIn	.3.1.6.107	Number of bytes received from local clients (counter; integer)
netcheckLocalBytesOut	.3.1.6.108	Number of bytes sent back to local clients (counter; integer)
netcheckNetworkBytesIn	.3.1.6.109	Number of bytes received from remote hosts (counter; integer)
netcheckNetworkBytesOut	.3.1.6.110	Number of bytes sent to remote hosts (counter; integer)





Parameter name	OID parameter	Type and description of the parameter
netcheckLocalScanErrors	.3.1.6.111	Number of error occurrences in local scan engine processes (counter; integer)
netcheckNetworkScanErrors	.3.1.6.112	Number of error occurrences in remote scan engine processes (counter; integer)
<i>httpd</i>	.3.1.7	drweb-httpd component data
httpdState	.3.1.7.1	Component status (integer****)
httpdExitCode	.3.1.7.2	Last exit code (an integer corresponding to codes from the error catalog)
httpdExitTime	.3.1.7.3	Termination time ( <i>UNIX time</i> )
<i>snmpd</i>	.3.1.8	drweb-snmpd component data
snmpdState	.3.1.8.1	Component status (integer****)
snmpdExitCode	.3.1.8.2	Last exit code (an integer corresponding to codes from the error catalog)
snmpdExitTime	.3.1.8.3	Termination time ( <i>UNIX time</i> )
<i>statd</i>	.3.1.9	drweb-statd component data
statdState	.3.1.9.1	Component status (integer****)
statdExitCode	.3.1.9.2	Last exit code (an integer corresponding to codes from the error catalog)
statdExitTime	.3.1.9.3	Termination time ( <i>UNIX time</i> )
statdConnectionsIn	.3.1.9.101	Number of accepted incoming connections (counter; integer)
statdConnectionsCount	.3.1.9.102	Number of currently established connections (counter; integer)
<i>smb spider</i>	.3.1.40	drweb-smb spider-daemon component data
smb spiderState	.3.1.40.1	Component status (integer****)



Parameter name	OID parameter	Type and description of the parameter
smbspiderExitCode	.3.1.40.2	Last exit code (an integer corresponding to codes from the error catalog)
smbspiderExitTime	.3.1.40.3	Termination time ( <i>UNIX time</i> )
smbspiderConnectionsIn	.3.1.40.101	Total number of established connections (counter; integer)
smbspiderConnectionsCount	.3.1.40.102	Number of currently established connections (counter; integer)
smbspiderShareTable	.3.1.40.103	Statistics on the protected Samba resources
<i>smbspiderShareEntry</i>	.3.1.40.103.1	Information about the protected Samba resource (table row; record)
smbspiderShareIndex	.3.1.40.103.1.1	Index (number) of the protected Samba resource (integer)
smbspiderSharePath	.3.1.40.103.1.2	Path to the protected Samba resource (string)
smbspiderShareConnectionsIn	.3.1.40.103.1.3	Total number of established connections (counter; integer)
smbspiderShareConnectionsCount	.3.1.40.103.1.4	Number of currently established connections (counter; integer)
<i>meshd</i>	.3.1.52	drweb-meshd component data
meshdState	.3.1.52.1	Component status (integer****)
meshdExitCode	.3.1.52.2	Last exit code (an integer corresponding to codes from the error catalog)
meshdExitTime	.3.1.52.3	Termination time ( <i>UNIX time</i> )
<i>linuxspider</i>	.3.1.201	drweb-spider (for GNU/Linux) component data
linuxspiderState	.3.1.201.1	Component status (integer****)
linuxspiderExitCode	.3.1.201.2	Last exit code (an integer corresponding to codes from the error catalog)



Parameter name	OID parameter	Type and description of the parameter
linuxspiderExitTime	.3.1.201.3	Termination time ( <i>UNIX time</i> )
linuxspiderWorkStatus	.3.1.201.101	Component operation mode (integer: 0—not specified, 1—loading, 2—running via fanotify)
ctl	.3.1.300	drweb-ctl component data
ctlState	.3.1.300.1	Component status (integer****)
ctlExitCode	.3.1.300.2	Last exit code (an integer corresponding to codes from the error catalog)
ctlExitTime	.3.1.300.3	Termination time ( <i>UNIX time</i> )
license	.3.2	License status
licenseEsMode	.3.2.1	The license has been granted by the centralized protection server (integer: 0—no, 1—yes)
licenseNumber	.3.2.2	License number (integer)
licenseOwner	.3.2.3	License owner (string)
licenseActivated	.3.2.4	License activation date ( <i>UNIX time</i> )
licenseExpires	.3.2.5	License expiration date ( <i>UNIX time</i> )

\*) Threat types:

Code	Threat Type
1	Known virus ( <i>known virus</i> )
2	Suspicious object ( <i>suspicious</i> )
3	Adware ( <i>adware</i> )
4	Dialer ( <i>dialer</i> )
5	Joke ( <i>joke program</i> )
6	Riskware ( <i>riskware</i> )
7	Hacktool ( <i>hacktool</i> )



\*\* ) URL categories:

Code	Threat Type
1	Infection source ( <i>infectionSource</i> )
2	Not recommended ( <i>notRecommended</i> )
3	Adult content ( <i>adultContent</i> )
4	Violence ( <i>violence</i> )
5	Weapons ( <i>weapons</i> )
6	Gambling ( <i>gambling</i> )
7	Drugs ( <i>drugs</i> )
8	Obscene language ( <i>obsceneLanguage</i> )
9	Chats ( <i>chats</i> )
10	Terrorism ( <i>terrorism</i> )
11	Free email ( <i>freeEmail</i> )
12	Social networks ( <i>socialNetworks</i> )
13	URL added due to a notice from copyright owner ( <i>ownerNotice</i> )
14	Online games ( <i>onlineGames</i> )
15	Anonymizers ( <i>anonymizers</i> )
16	Cryptocurrency mining pools ( <i>cryptocurrencyMiningPools</i> )
17	Jobs ( <i>Jobs</i> )
20	Black list ( <i>blackList</i> )

\*\*\* ) Codes of Dr.Web components:

Code	Component
1	Dr.Web ConfigD ( <i>drweb-configd</i> )
2	Dr.Web Scanning Engine ( <i>drweb-se</i> )
3	Dr.Web File Checker ( <i>drweb-filecheck</i> )
4	Dr.Web Updater ( <i>drweb-update</i> )



Code	Component
5	Dr.Web ES Agent (drweb-esagent)
6	Dr.Web Network Checker (drweb-netcheck)
7	Dr.Web HTTPD (drweb-httpd)
8	Dr.Web SNMPD (drweb-snmpd)
40	SpIDer Guard for SMB (drweb-smbspider-daemon)
52	Dr.Web MeshD (drweb-meshd)
201	SpIDer Guard (drweb-spider)
300	Dr.Web Ctl (drweb-ctl)
400	Scanning tasked by a centralized protection server (not a component of Dr.Web Industrial for UNIX File Servers)

\*\*\*\*) Possible states of the components:

Code	Status
0	Not installed
1	Installed but not started
2	Is starting
3	Is running
4	Is exiting

To get the values of the variables directly, you can use the `snmpwalk` utility:

```
$ snmpwalk -Os -c <community> -v <SNMP version> <host address> <OID>
```

For example, to get statistics about the threats detected on the local host, use the following command (if Dr.Web SNMPD has default settings):

```
$ snmpwalk -Os -c public -v 2c 127.0.0.1 .1.3.6.1.4.1.29690.2.2.1
```



## Dr.Web MeshD

Dr.Web MeshD is an agent that includes the host with Dr.Web Industrial for UNIX File Servers installed in a “local cloud” that connects hosts with installed Dr.Web for UNIX products. This cloud allows to solve the following tasks:

- providing other file scanning services by several cloud hosts (a scanning core service);
- distributing updates for virus databases between cloud hosts.

To connect hosts with Dr.Web for UNIX products installed, the Dr.Web MeshD component must be installed on every host. The component includes the host into the cloud. Host’s rights within the cloud and cloud features that are used by the host, can be easily configured by Dr.Web MeshD settings.

Data is shared with other cloud hosts over a protected SSH channel.

## Operating Principles

### In this section

- [Connection types](#)
- [Operation modes](#)
- [Services](#)

Dr.Web MeshD mediates interaction between a host with Dr.Web Industrial for UNIX File Servers installed and other cloud hosts.

### Connection types

Dr.Web MeshD uses the following connection types:

- *Client (service)*—used by Dr.Web MeshD to connect to other cloud hosts. These hosts are clients of services provided by the given host.



Components of Dr.Web Industrial for UNIX File Servers operating on the host and accessing services provided by the cloud through Dr.Web MeshD operating on the same host connect to it via a local UNIX socket. At that, a client connection is not used.

- *Partner (peer to peer)*—used by Dr.Web MeshD for interaction with peer (within a service) partner cloud hosts. Usually such horizontal connections are used for scaling and distributing the load when interacting with the cloud, as well as for synchronization of cloud hosts.
- *Uplink*—used by Dr.Web MeshD to connect this host (client) to cloud hosts (service providers) (for example, distribution of virus databases updates, file transmission for scanning, and so on).



The use of all three types of connections is configured independently for different cloud services. At that, the same host can be configured as a server for processing client requests within a service (for example, providing fresh updates) and as a client within another service (for example, remote file scanning).

Within cloud, hosts perform authorized interaction via a secure SSH protocol, that is, all sides of interhost communication are always mutually authenticated. For the authentication, *host keys* are used according to [RFC 4251](#). The client connection from the local component is always considered as trusted.

## Operation Modes

Dr.Web MeshD can work both in the daemon mode and run on requests from other Dr.Web Industrial for UNIX File Servers components, located on the local host. If Dr.Web MeshD is configured to serve client connections (i.e. the `ListenAddress` parameter is not empty) and at least one of the services is activated, Dr.Web MeshD starts as a daemon and waits for connections from clients. Besides, Dr.Web MeshD can be activated on the local host upon request, for example, when executing the [command](#):

```
$ drweb-ctl update --local-cloud
```

If Dr.Web MeshD is not set to process client connections (the `ListenAddress` parameter is empty) and there is no request to Dr.Web MeshD during the period specified in the `IdleTimeLimit` parameter, the component exits automatically.

## Services

### Exchanging updates (Update)

The service allows the host to subscribe to updates of virus and other databases, send notifications on the updates, upload and share the update files between cloud hosts. The service settings can be configured using the `Update*` parameters.

The standard service usage assumes that Dr.Web MeshD is installed with the enabled feature of obtaining updates on several machines (clients of the service) in the local network of the company. The typical client [settings](#) are:

```
...
[MeshD]
UpdateChannel = On
UpdateUplink = <server address>
ListenAddress =
...
[Update]
UseLocalCloud = Yes
...
```



On the local server for distributing updates, the following settings are specified:

```
UpdateChannel = On
UpdateUplink =
ListenAddress = <address>:<port>
```

Here, *<server address>* in the uplink connection of the client must refer to the *<address>* and *<port>* that are used by the server host for managing client connections.

When one of the hosts is being updated from the update servers (external to the local cloud—Dr.Web GUS update servers or the centralized protection server), the host sends a notification to all necessary clients (if the host is set as an update exchange server) and sends to the server host a new list of files available for distribution from the host. Upon receiving the notification, client hosts can request the update download from the server, that in turn can request the files from the client to save them locally or to send them to the other client that has the requested files from the server.

The scenario decreases the update delay because clients send requests to Dr.Web GUS at different times, at thus the first updated client immediately distributes the fresh update files to all necessary cloud hosts. It also decreases amount of traffic and Dr.Web GUS load.



Note that when using the local cloud for update distribution, in addition to Dr.Web MeshD, hosts must contain the Dr.Web Updater component.

### Remote file scanning (Engine)

The service allows to use Dr.Web Scanning Engine for scanning remote files: client hosts send files for scanning to the server host and server hosts provide a service for file scanning. The typical client [settings](#) are:

```
...
[MeshD]
EngineChannel = On
EngineUplink = <server address>
ListenAddress =
...
```

On the local scanning server, the following settings are specified:

```
EngineChannel = On
EngineUplink =
ListenAddress = <address>:<port>
```

Here, *<server address>* in the uplink connection of the client must refer to the *<address>* and *<port>* that are used by the server host for managing client connections.





## Transmitting files for scanning (File)

The feature is not used (remote scanning is provided within the *Engine* service).

## URL check

The service allows to use the server hosts to check URL for belonging to potentially dangerous and non-recommended categories: client hosts send URL to be checked to the server host. The typical client [settings](#) are:

```
...  
[MeshD]  
UrlChannel = On  
UrlUplink = <server address>  
ListenAddress =  
...
```

On the local server used for URL check, the following settings are specified:

```
UrlChannel = On  
UrlUplink =  
ListenAddress = <address>:<port>
```

Here, <server address> in the uplink connection of the client must refer to the <address> and <port> that are used by the server host for managing client connections.



## Command-Line Arguments

To run Dr.Web MeshD, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-meshd [<parameters>]
```

Dr.Web MeshD can process the following options:

Parameter	Description
--help	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> -h <b>Arguments:</b> None.
--version	<b>Function:</b> Instructs to output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> -v <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-meshd --help
```

This command outputs short help information on Dr.Web MeshD.

## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically when needed by the [Dr.Web ConfigD](#) configuration daemon. To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-meshd`.

## Configuration Parameters

The component uses configuration parameters which can be found in the [MeshD] section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.



The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <a href="#">[Root]</a> <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
<code>Log</code> <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
<code>ExePath</code> <i>{path to file}</i>	<p>Executable path to the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-meshd</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-meshd</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-meshd</code></li></ul>
<code>DebugSsh</code> <i>{Boolean}</i>	<p>Performing logging of the SSH protocol messages (used for transferring messages and data) received and sent by Dr.Web MeshD operating on the host, if logging level is <code>LogLevel = Debug</code>.</p> <p>Default value: <code>No</code></p>
<code>IdleTimeLimit</code> <i>{time interval}</i>	<p>Maximum idle time for the component. When the specified period of time expires, the component shuts down.</p> <p>Acceptable values: from 10 seconds (<code>10s</code>) to 30 days (<code>30d</code>) inclusive.</p> <p>If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the component goes idle.</p> <p>Default value: <code>30s</code></p>
<code>DnsResolverConfPath</code> <i>{path to file}</i>	<p>Path to the subsystem configuration file of domain name permissions (DNS resolver).</p> <p>Default value: <code>/etc/resolv.conf</code></p>
<code>ListenAddress</code> <i>&lt;IP address&gt;:&lt;port&gt;</i>	<p>Network socket (address and port) of the client connection where the component is waiting to receive the connections from cloud hosts. These hosts are clients of services provided by this cloud host.</p> <p>In order for the component to listen on the IPv6 interface and detect cloud client hosts via IPv6, the parameter must be set.</p> <p>If the value is not specified, the component does not receive requests from clients.</p> <p>Default value: <i>(not set)</i></p>
<code>UpdateChannel</code> <i>{On   Off}</i>	<p>Enabling or disabling the Dr.Web MeshD component working on this host, exchanging updates of virus databases between hosts of the cloud (for example, getting updates of virus databases from other cloud hosts and sending new updates to the cloud).</p>



Parameter	Description
	<p>If the parameter is set to On, the component Dr.Web MeshD is automatically started by the Dr.Web ConfigD configuration daemon.</p> <p>Default value: On</p>
UpdateUplink {address}	<p>Address of the upper host of Dr.Web MeshD that acts as a server providing URL checking services for this host.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <i>value is not specified</i>—server is not set for the service and Dr.Web MeshD will not connect to anywhere;</li><li>• <i>&lt;IP address&gt;:&lt;port&gt;</i>—Dr.Web MeshD will connect to the server with the specified address and port;</li><li>• <i>dns : &lt;service name&gt; [ : &lt;domain&gt; ]</i>—address and port of the server is determined by searching for SRV record of the <i>&lt;domain&gt;</i> DNS domain. If <i>&lt;domain&gt;</i> is not specified, a domain from the DNS resolver configuration file is used (the path is specified in <i>ResolverConfPath</i>). The domain is taken from the <i>search</i> or <i>domain</i> field, depending on which of them is encountered last;</li><li>• <i>discover</i>—search for the higher host by the <i>discovery</i> mechanism.</li></ul> <p>Default value: (not specified)</p>
UpdateDebugIpc {Boolean}	<p>Output the debug information to the log for the update exchange service if logging level is <i>LogLevel = Debug</i>.</p> <p>Default value: No</p>
UpdateTraceContent {Boolean}	<p>Output the transmitted data to the log for the update exchange service if logging level is <i>LogLevel = Debug</i>.</p> <p>Default value: No</p>
FileChannel {On   Off}	<p>Enable or disable an option that allows the Dr.Web MeshD component that works on this host to participate in exchanging files.</p> <p>If the parameter is set to On, the component Dr.Web MeshD is automatically started by the Dr.Web ConfigD configuration daemon.</p> <p>Default value: On</p>
FileUplink {address}	<p>Address of the higher host of Dr.Web MeshD that acts as a server which scans files from this host.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <i>value is not specified</i>—server is not set for the service and Dr.Web MeshD will not connect to anywhere;</li><li>• <i>&lt;IP address&gt;:&lt;port&gt;</i>—Dr.Web MeshD will connect to the server with the specified address and port;</li><li>• <i>dns : &lt;service name&gt; [ : &lt;domain&gt; ]</i>—address and port of the server is determined by searching for SRV record of the <i>&lt;domain&gt;</i> DNS domain. If</li></ul>



Parameter	Description
	<p>&lt;domain&gt; is not specified, a domain from the DNS resolver configuration file is used (the path is specified in <code>ResolverConfPath</code>). The domain is taken from the <code>search</code> or <code>domain</code> field, depending on which of them is encountered last;</p> <ul style="list-style-type: none"><li>• <code>discover</code>—search for the higher host by the <i>discovery</i> mechanism.</li></ul> <p>Default value: <i>(not specified)</i></p>
<code>FileDebugIpc</code> {Boolean}	<p>Output the debug information to the log for the file exchange service if logging level is <code>LogLevel = Debug</code>.</p> <p>Default value: <code>No</code></p>
<code>EngineChannel</code> {On   Off}	<p>Enable or disable an option that allows the Dr.Web MeshD component that works on this host to participate providing scan engine services.</p> <p>If the parameter is set to <code>On</code>, the component Dr.Web MeshD is automatically started by the Dr.Web ConfigD configuration daemon.</p> <p>Default value: <code>On</code></p>
<code>EngineUplink</code> {address}	<p>Address of the higher host of Dr.Web MeshD that acts as a scanning server which provides the scan engine services for this host.</p> <p>Allowed values:</p> <ul style="list-style-type: none"><li>• <i>value is not specified</i>—server is not set for the service and Dr.Web MeshD will not connect to anywhere;</li><li>• <code>&lt;IP address&gt;:&lt;port&gt;</code>—Dr.Web MeshD will connect to the server with the specified address and port;</li><li>• <code>dns:&lt;service name&gt;[:&lt;domain&gt;]</code>—address and port of the server is determined by searching for SRV record of the &lt;domain&gt; DNS domain. If &lt;domain&gt; is not specified, a domain from the DNS resolver configuration file is used (the path is specified in <code>ResolverConfPath</code>). The domain is taken from the <code>search</code> or <code>domain</code> field, depending on which of them is encountered last;</li><li>• <code>discover</code>—search for the higher host by the <i>discovery</i> mechanism.</li></ul> <p>Default value: <i>(not specified)</i></p>
<code>EngineDebugIpc</code> {Boolean}	<p>Output the debug information to the log for the scan service if logging level is <code>LogLevel = Debug</code>.</p> <p>Default value: <code>No</code></p>
<code>UrlChannel</code> {On   Off}	<p>Enable or disable an option that allows the Dr.Web MeshD component that works on this host to participate providing URL check services.</p> <p>Default value: <code>On</code></p>
<code>UrlUplink</code> {address}	<p>Address of the higher host of Dr.Web MeshD that acts as a server which provides the URL check services for this host.</p>



Parameter	Description
	<p>Allowed values:</p> <ul style="list-style-type: none"><li>• <i>value is not specified</i>—server is not set for the service and Dr.Web MeshD will not connect to anywhere;</li><li>• <i>&lt;IP address&gt;:&lt;port&gt;</i>—Dr.Web MeshD will connect to the server with the specified address and port;</li><li>• <i>dns : &lt;service name&gt; [ : &lt;domain&gt; ]</i>—address and port of the server is determined by searching for SRV record of the <i>&lt;domain&gt;</i> DNS domain. If <i>&lt;domain&gt;</i> is not specified, a domain from the DNS resolver configuration file is used (the path is specified in <code>ResolverConfPath</code>). The domain is taken from the <code>search</code> or <code>domain</code> field, depending on which of them is encountered last;</li><li>• <i>discover</i>—search for the higher host by the <i>discovery</i> mechanism.</li></ul> <p>Default value: <i>(not specified)</i></p>
<code>DiscoveryResponderPort</code> <i>{port number}</i>	<p>The port on which the higher host responds to the requests of the clients set via UDP protocol.</p> <p>The <i>discovery</i> mechanism is activated only if the <code>ListenAddress</code> value is set.</p> <p>Default value: 18008</p>
<code>UrlDebugIpc</code> <i>{Boolean}</i>	<p>Output the debug information to the log for the URL check service if logging level is <code>LogLevel = Debug</code>.</p> <p>Default value: No</p>



The current version of Dr.Web Industrial for UNIX File Servers, the *File* file-transmitting service is not used. Use the *Engine* scan engine service instead.



## Dr.Web StatD

The Dr.Web StatD component is designed for accumulating statistics of events that occur during the operation of Dr.Web Industrial for UNIX File Servers components. The events are stored in the permanent repository and can be obtained on request.

## Operating Principles

The component ensures accumulation and permanent storage of events obtained during the operation of Dr.Web Industrial for UNIX File Servers components. The following types of events are logged:

- Component emergency shutdown;
- Threat detection (in email messages, among other sources).

Dr.Web StatD works in the daemon mode and is automatically launched by the configuration control daemon. Event viewing and management is ensured by the [command](#) `events` of the [Dr.Web Ctl](#) utility.

## Command-Line Arguments

To run Dr.Web StatD, type the following command in the command line:

```
$ <opt_dir>/bin/drweb-statd [<parameters>]
```

Dr.Web StatD can process the following options:

Parameter	Description
<code>--help</code>	<b>Function:</b> Output short help information about command-line parameters to the console or to the terminal emulator and to exit upon completion. <b>Short form:</b> <code>-h</code> <b>Arguments:</b> None.
<code>--version</code>	<b>Function:</b> Output information about the version of this component to the console or to the terminal emulator and to exit after completion. <b>Short form:</b> <code>-v</code> <b>Arguments:</b> None.

### Example:

```
$ /opt/drweb.com/bin/drweb-statd --help
```

This command outputs short help information on Dr.Web StatD.



## Startup Notes

The component cannot be launched directly from the command line of the operating system in an autonomous mode (autonomously from other components). It is launched automatically by the [Dr.Web ConfigD](#) configuration daemon when needed. To manage the operation of the component, you can use the [Dr.Web Ctl](#) command-line-based management tool for Dr.Web Industrial for UNIX File Servers (it is called by using the `drweb-ctl` [command](#)).



To request documentation about this component of the product from the command line, use the following command `man 1 drweb-statd`.

## Configuration Parameters

The component uses configuration parameters which can be found in the `[StatD]` section of the integrated [configuration file](#) of Dr.Web Industrial for UNIX File Servers.

The section contains the following parameters:

Parameter	Description
<code>LogLevel</code> <i>{logging level}</i>	<p><a href="#">Logging level</a> of the component.</p> <p>If the parameter value is not specified, the <code>DefaultLogLevel</code> parameter value from the <code>[Root]</code> <a href="#">section</a> is used.</p> <p>Default value: <code>Notice</code></p>
<code>Log</code> <i>{log type}</i>	<p><a href="#">Logging method</a> of the component.</p> <p>Default value: <code>Auto</code></p>
<code>ExePath</code> <i>{path to file}</i>	<p>Executable path to the file of the component.</p> <p>Default value: <code>&lt;opt_dir&gt;/bin/drweb-statd</code>.</p> <ul style="list-style-type: none"><li>• For GNU/Linux: <code>/opt/drweb.com/bin/drweb-statd</code>.</li><li>• For FreeBSD: <code>/usr/local/libexec/drweb.com/bin/drweb-statd</code></li></ul>
<code>RunAsUser</code> <i>{UID   user name}</i>	<p>The name of the user on whose behalf the component is run. The user name can be specified either as the user's number UID or as the user's login. If the user name consists of numbers (i.e. similar to number UID), it is specified with the "name:" prefix, for example:</p> <p><code>RunAsUser = name:123456</code>.</p> <p>When a user name is not specified, the component operation terminates with an error after the startup.</p> <p>Default value: <code>drweb</code></p>





Parameter	Description
<code>IdleTimeLimit</code> <i>{time interval}</i>	<p>Maximum idle time for the component. When the specified period of time expires, the component shuts down.</p> <p>Acceptable values: from 10 seconds (10s) to 30 days (30d) inclusive. If the <code>None</code> value is set, the component will functionate eternally; the <code>SIGTERM</code> signal will not be sent if the components goes idle.</p> <p>Default value: 30s</p>
<code>MaxEventStoreSize</code> <i>{size}</i>	<p>Maximum allowed size of the event database. Defined in <code>mb</code>, for example: <code>MaxEventStoreSize = 100mb</code>.</p> <p>Minimum value: 50mb.</p> <p>Default value: 1GB</p>



## Appendices

### Appendix A. Types of Computer Threats

Herein, the term “*threat*” is defined as any kind of software potentially or directly capable of inflicting damage to a computer or network and compromising the user’s information or rights (that is, malicious and other unwanted software). In a wider sense, the term “*threat*” may be used to indicate any type of potential danger to the security of the computer or network (that is, vulnerabilities that can result in hacker attacks).

All of the program types stated below have the ability to endanger user data or confidentiality. Programs that do not conceal their presence in the system (e.g. spam distribution software and various traffic analyzers) are usually not considered as computer threats, although they can become threats under certain circumstances.

#### Computer Viruses

This type of computer threats is characterized by the ability to embed its code into other programs. Such implementation is called infection. In most cases, an infected file becomes a virus carrier and the embedded code does not necessarily match the original one. Most viruses are intended to damage or destroy data in the system.

In Doctor Web classification, viruses are divided by the type of objects they infect:

- *File viruses* infect files of the operating system (usually executable files and dynamic libraries) and are activated when the infected file is launched.
- *macro-viruses* are viruses that infect documents used by Microsoft® Office and some other applications supporting macro commands (for example, written in Visual Basic). *Macro commands* are a type of implemented programs (macros) written in a fully functional programming language. For instance, in Microsoft® Word, macros can be automatically initiated upon opening, closing, or saving a document.
- *Script viruses* are created using script languages and usually infect other scripts (e.g. service files of an operating system). They are also able to infect other file formats that allow execution of scripts and thus take advantage of scripting vulnerabilities in web applications.
- *boot viruses* infect boot records of disks and partitions or master boot records of hard drives. They do not require much memory and remain ready to continue performing their tasks until a system roll-out, restart or shut-down is performed.

Most viruses have some kind of protection against detection. Protection methods are being constantly improved, and ways to overcome them are constantly being developed. All viruses may also be classified according to protection type they use:

- *Encrypted viruses* cipher their code upon every infection to hamper their detection in a file, boot sector or memory. All copies of such viruses contain only a small common code fragment (the decryption procedure) that can be used as a virus signature.



- *Polymorphic viruses* also encrypt their code, but besides that they also generate a special decryption procedure that is different in every copy of the virus. This means that such viruses do not have byte signatures.
- *Stealth viruses* perform certain actions to disguise their activity and thus conceal their presence in an infected object. Such viruses gather the characteristics of an object before infecting it and then plant these “dummy” characteristics that mislead the scanner searching for modified files.

Viruses can also be classified according to the programming language in which they are written (in most cases, it is Assembler, high-level programming languages, script languages, and so on) or according to affected operating systems.

## Computer Worms

Recently, malicious programs of the “computer worm” type have become much more common than viruses and other types of malware. Just like viruses, such programs can make copies of themselves, however they do not infect other objects. A worm gets into a computer from a network (most frequently as an attachment to an email or from the internet) and sends the functioning copies of itself to other computers. To start their spread, worms can either rely on the computer user’s actions or can select and attack computers in an automatic mode.

Worms do not necessarily consist of only one file (the worm’s body). Many of them have an infectious part (the shellcode) that loads into the main memory (RAM) and then downloads the worm’s body as an executable file via the network. If only the shellcode is present in the system, the worm can be deleted by simply restarting the system (at which the RAM is erased and reset). However, if the worm’s body infiltrates the computer, then only an anti-virus program can cope with it.

Worms have the ability to cripple entire networks even if they do not bear any payload (i.e. do not cause any direct damage) due to their intensive distribution.

In Doctor Web classification, worms are divided by distribution method:

- *Net worms* distribute their copies via various network and file-sharing protocols.
- *mail worms* spread themselves using email protocols (POP3, SMTP, and so on).
- *chat worms* use protocols of popular messengers and chat programs (ICQ, IM, IRC, and so on).

## Trojan Programs (Trojans)

This type of threats cannot reproduce itself. A trojan substitutes a frequently-used program and performs its functions (or imitates its operation). Meanwhile, it performs some malicious actions in the system (damages or deletes data, sends confidential information, and so on) or makes it possible for hackers to access the computer without permission, for example, to harm the computer of a third party.



A trojan masking and malicious facilities are similar to those of a virus. A trojan may even be a component of a virus. However, most trojans are distributed as separate executable files (through file exchange servers, removable data carriers or email attachments) that are launched by users or system tasks.

It is very hard to classify trojans due to the fact that they are often distributed by viruses or worms and also because many malicious actions that can be performed by other types of threats are attributed to trojans only. Here are some trojan types which are distinguished as separate classes in Doctor Web:

- *backdoors* are trojans that make it possible for an intruder to log on into the system or obtain privileged functions bypassing any existing access and security measures. Backdoors do not infect files, but they write themselves into the registry modifying the registry keys.
- *rootkits* are used to intercept system functions of an operating system in order to conceal themselves. Besides, a rootkit can conceal processes of other programs (e.g. other threats), registry keys, folders and files. It can be distributed either as an independent program or as a component of another malicious program. There are two kinds of rootkits according to the mode of operation: *User Mode Rootkits (UMR)* that operate in user mode (intercept functions of the user mode libraries) and *Kernel Mode Rootkits (KMR)* that operate in kernel mode (intercept functions on the level of the system kernel, which makes it harder to detect).
- *keyloggers* are used to log data that users enter by means of a keyboard. The aim of this is to steal personal information (i.e. network passwords, logins, credit card data, and so on).
- *clickers* redirect hyperlinks to certain addresses (sometimes malicious) in order to increase traffic of websites or perform DDoS attacks.
- *Proxy trojans* provide anonymous internet access through a victim's computer.

In addition, trojans can also change the start page in a web browser or delete certain files. However, these actions can also be performed by other types of threats (viruses and worms).

## Hacktools

Hacktools are programs designed to assist the intruder with hacking. The most common among them are port scanners that detect vulnerabilities in firewalls and other components of computer protection system. Besides hackers, such tools are used by administrators to check security of their networks. Occasionally, common software that can be used for hacking and various programs that use social engineering techniques are designated as among hacktools as well.

## Adware

Usually, this term refers to a program code implemented into freeware programs that force display of advertisements to users. However, sometimes such codes can be distributed via other malicious programs and show advertisements in web browsers. Many adware programs operate with data collected by spyware.



## Jokes

Like adware, this type of minor threats can not be used to inflict any direct damage to the system. Joke programs usually just generate messages about errors that never occurred and threaten to perform actions that will lead to data loss. Their purpose is to frighten or annoy users.

## Dialers

These are special programs that are designed to scan a range of telephone numbers and find those where a modem answers. These numbers are then used to mark up the price of telephoning facilities or to connect the user to expensive telephone services.

## Riskware

These software applications were not created for malicious purposes, but due to their characteristics can pose a threat to the computer security. Riskware programs can not only damage or delete data, but they are also used by crackers (i.e. malevolent hackers) or by some malicious programs to harm the system. Among such programs, there are various remote chat and administrative tools, FTP-servers, and so on.

## Suspicious objects

These are possible computer threats detected by the heuristic analyzer. Such objects can potentially be any type of threat (even unknown to IT security specialists) or turn out to be safe in case of false detection. It is recommended that you choose to move the files containing suspicious objects to the quarantine, they also should be sent to Doctor Web anti-virus laboratory for analysis.



## Appendix B. Neutralizing Computer Threats

### In this appendix

- [Detection Methods](#)
- [Threat-related Actions](#)

All Doctor Web anti-virus solutions use several malicious software detection methods simultaneously, and that allows them to perform thorough scans for suspicious files and control software behavior.

## Detection Methods

### Signature Analysis

Signature analysis is the first stage of detection procedure and is used to check file code segments for the presence of known virus signatures. A signature is a finite continuous sequence of bytes necessary and sufficient to identify a specific virus. To reduce the size of the signature dictionary, Dr.Web anti-virus solutions use signature checksums instead of complete signature sequences. Checksums uniquely identify signatures, which preserves correctness of virus detection and neutralization. The Dr.Web virus databases are composed so that some entries can be used to detect not just specific viruses, but whole classes of threats.

### Origins Tracing™

On completion of signature analysis, Dr.Web anti-virus solutions use the unique Origins Tracing™ method to detect new and modified viruses which use the known infection mechanisms. Thus, Dr.Web users are protected against such threats as the notorious Trojan.Encoder.18 ransomware (also known as gpcode). In addition to detection of new and modified viruses, the Origins Tracing™ mechanism allows to considerably reduce the number of false positives of the heuristics analyzer. Objects detected using the Origins Tracing™ algorithm are indicated with the `.Origin` extension added to their names.

### Execution Emulation

The technology of program code emulation is used for detection of polymorphic and encrypted viruses when a search by checksums cannot be applied directly, or is very difficult to be performed (due to the impossibility of building secure signatures). The method implies simulating the execution of an analyzed code by an *emulator*—a programming model of the processor and runtime environment. An emulator operates with protected memory area (*emulation buffer*), in which execution of the analyzed program is modelled instruction by instruction. However, none of these instructions is actually executed by the CPU. When the emulator receives a file infected with a polymorphic virus, the result of the emulation is a



decrypted virus code, which is then easily determined by searching against signature checksums.

## Heuristic Analysis

The detection method used by the heuristics analyzer is based on certain knowledge (*heuristics*) about certain features (attributes) than might be typical for the virus code itself, and vice versa, that are extremely rare in viruses. Each attribute has a *weight* coefficient which determines the level of its severity and reliability. The weight coefficient can be positive if the corresponding attribute is indicative of a malicious code or negative if the attribute is uncharacteristic of a computer threat. Depending on the sum weight of a file, the heuristics analyzer calculates the probability of unknown virus infection. If the threshold is exceeded, the heuristic analyzer generates the conclusion that the analyzed object is probably infected with an unknown virus.

The heuristics analyzer also uses the FLY-CODE™ technology, which is a versatile algorithm to extract packed files. The technology allows making heuristic assumptions about the presence of malicious objects in files compressed not only by packers that Dr.Web is aware of, but by also new, previously unexplored programs. While scanning packed objects, Dr.Web Anti-virus solutions also use structural entropy analysis. The technology detects threats by the characteristic way in which pieces of code are arranged inside a file; thus, one virus database entry allows identification of a substantial portion of threats packed with the same polymorphous packer.

As any system of hypothesis testing under uncertainty, the heuristics analyzer may commit type I or type II errors (omit viruses or raise false positives). Thus, objects detected by the heuristics analyzer are treated as “suspicious”.

While performing any of the scans previously mentioned, Dr.Web anti-virus solutions use the most recent information about known malicious software. As soon as experts of Doctor Web anti-virus laboratory discover new threats, an update for virus signatures, behavior characteristics and attributes is issued. In some cases updates can be issued several times per hour. Therefore even if a brand new malicious program passes through the Dr.Web resident guards and penetrates the system, then after an update the malicious program is detected in the list of processes and neutralized.

## Actions

To avert computer threats, Dr.Web products use a number of actions that can be applied to malicious objects. A user can leave the default settings, configure which actions to apply automatically, or choose actions manually upon every detection. Below, you can see a list of available actions:

- **Ignore** (*Ignore*)—instructs to skip the detected threat without performing any other action.
- **Report** (*Report*)—instructs to inform on the detected threat without performing any other action.



- **Block** (*Block*)—instructs to block all attempts to access the infected file (the action might not be available for all components).
- **Cure** (*Cure*)—instructs to cure the infected object by removing only malicious content from its body. Note that this action cannot be applied to all types of threats.
- **Quarantine** (*Quarantine*)—instructs to move the detected threat to a special directory and isolate it from the rest of the system.
- **Delete** (*Delete*)—instructs to remove the infected object permanently.



If threat is detected in a file located in a container (an archive, email message, and so on), its removal is replaced with moving of a container to quarantine.

## Appendix C. Technical Support

If you have a problem installing or using Doctor Web products, please try the following before contacting technical support:

1. Download and review the latest manuals and guides at <https://download.drweb.com/doc/>.
2. See the Frequently Asked Questions section at [https://support.drweb.com/show\\_faq/](https://support.drweb.com/show_faq/).
3. Browse the official Doctor Web forum at <https://forum.drweb.com/>.

If you haven't found a solution to your problem, you can request direct assistance from Doctor Web technical support specialists. Please use one of the options below:

1. Fill out a web form in the appropriate section at <https://support.drweb.com/>.
2. Call +7 (495) 789-45-86 (for customers in Moscow) or 8-800-333-79-32 (a toll-free line for customers within Russia).

For information on regional and international offices of Doctor Web, please visit the official website at <https://company.drweb.com/contacts/offices/>.

To facilitate processing of your issue, we recommend that you generate a data set for the installed product, its configuration, and system environment before contacting the technical support. To do that, you can use a special utility included in the Dr.Web Industrial for UNIX File Servers distribution.

To collect the data for technical support, use the command:

```
# <opt_dir>/bin/support-report.sh
```

where `<opt_dir>` is a directory for Dr.Web Industrial for UNIX File Servers files, including executables and libraries (`/opt/drweb.com` by default for GNU/Linux). For details on conventions used for directories, refer to [Introduction](#).





To collect all data required for technical support, we recommend that you launch the utility with superuser privileges (i.e. privileges of the `root` user). To elevate your privileges, log in as a different user with the `su` command or use the `sudo` command to execute the command on behalf of another user.

During operation, the utility collects and archives the following information:

- OS data (name, architecture, result of the `uname -a` command);
- list of packages installed to your system, including Doctor Web packages;
- log contents:
  - Dr.Web Industrial for UNIX File Servers logs (if configured for separate components);
  - log of the `syslog` system daemon (`/var/log/syslog`, `/var/log/messages`);
  - log of a system package manager (`apt`, `yum`, etc.);
  - the `dmesg` log;
- output of the commands: `df`, `ip a` (`ifconfig -a`), `ldconfig -p`, `iptables-save`, `nft export xml`;
- information on settings and configuration of Dr.Web Industrial for UNIX File Servers:
  - list of downloaded virus databases (`drweb-ctl baseinfo -l`);
  - list of files from Dr.Web Industrial for UNIX File Servers directories and MD5 hash values of these files;
  - Dr.Web Virus-Finding Engine scan engine version and MD5 hash value;
  - configuration parameters of Dr.Web Industrial for UNIX File Servers (including contents of `drweb.ini`, rules, value files used in rules, Lua procedures, etc.);
  - user information and permissions retrieved from the key file, if Dr.Web Industrial for UNIX File Servers is running in the standalone mode.

An archive containing information on the product and its system environment will be saved to the home directory of the user that launched the utility. The file will be named as follows:

```
drweb.report.<timestamp>.tgz
```

where `<timestamp>` is a full timestamp of creating the report, down to milliseconds, for example: `20190618151718.23625`.



## Appendix D. Dr.Web Industrial for UNIX File Servers Configuration File

Configuration parameters of all the Dr.Web Industrial for UNIX File Servers components are managed by a special coordinating daemon Dr.Web ConfigD. These parameters are stored in the `drweb.ini` file, which default directory is `<etc_dir>` (for GNU/Linux `/etc/opt/drweb.com`).



The text configuration file stores only those parameters which values differ from the defaults. If a parameter is absent in the configuration file, its default value is used.

For details on conventions for `<opt_dir>`, `<etc_dir>`, and `<var_dir>`, refer to the [Introduction](#).

You can view the list of all available parameters, including those that are absent in the configuration file and have default values, by using the command:

```
$ drweb-ctl cfshow
```

You can change any parameter value in one of the two ways:

1. Specify the parameter in the configuration file (by editing the file in any text editor) and send SIGHUP signal to the configuration daemon (the `drweb-configd` component) in order to apply the changes. To do that, you can run the following [command](#):

```
# drweb-ctl reload
```

2. Type this command in the command line:

```
# drweb-ctl cfset <section> . <parameter> <new value>
```



This command can be executed only if the management tool Dr.Web Ctl is run with superuser privileges. To gain superuser privileges, use `su` or `sudo` command.

For further information about the `cfshow` and `cfset` command syntax of the command-line management tool Dr.Web Ctl (the `drweb-ctl` module), refer to the section [Dr.Web Ctl](#).

## File Structure

The configuration file has the following structure.

- The file content is divided into named sections. Possible names of these sections are strictly predefined and cannot be changed. The section name is specified in square brackets and is similar to the the Dr.Web Industrial for UNIX File Servers component name, which uses the



section parameters (except for [Root] [section](#), which stores all parameters of the configuration daemon Dr.Web ConfigD).

- The ';' or '#' characters in the configuration file indicate the beginning of a comment—all text following the characters is skipped by the Dr.Web Industrial for UNIX File Servers components while reading configuration parameters.
- Each of the lines in the file can contain only one parameter value:

```
<Parameter name> = <Value>
```

- All parameter names are strictly predefined and cannot be changed.
- All section and parameter names are case-insensitive. Parameter values, except for names of directories and files in paths (for UNIX-like OS) are also case-insensitive.
- The order of sections in the file as well as the order of parameters inside the sections are of no importance.
- Parameter values in the configuration file can be enclosed in quotation marks, and must be enclosed in quotation marks if they have white spaces.
- Some parameters can take multiple values. If so, the values are either separated with commas or specified several times in different lines of the configuration file. In the former case, white spaces around a comma are ignored. If a white space character is a part of a parameter value, the character must be enclosed in quotation marks.

You can specify multiple values as:

- 1) a comma-separated list:

```
Parameter = Value1, Value2, "Value 3"
```

- 2) a sequence of lines in the configuration file:

```
Parameter = Value2  
Parameter = Value1  
Parameter = "Value 3"
```

The order of values is arbitrary.



Path to files and directories are always enclosed into quotation marks when separated by commas, e.g:

```
ExcludedPaths = "/etc/file1", "/etc/file2"
```

If you represent as a set of path as a sequence of lines, quotation marks are not necessary:

```
ExcludedPaths = /etc/file1  
ExcludedPaths = /etc/file2
```

- If a parameter can take multiple values, it is indicated in the comments in the configuration file or in the text of the current manual.



For description of the configuration file sections, see description of the Dr.Web Industrial for UNIX File Servers components.

## Parameter Types

Configuration parameters can belong to the following types:

- *address*—network connection address specified as *<IP address>:<port>*;
- *boolean*—parameter having only two possible values: *Yes* or *No*;
- *integer*—a non-negative integer;
- *fractional number* — a non-negative number with a fractional part;
- *time interval*—a time interval, consisting of a non-negative integer and a suffix (letter), which stands for a time unit. The following suffixes can be used:
  - *w*—weeks (1w = 7d);
  - *d*—days (1d = 24h);
  - *h*—hours (1h = 60m);
  - *m*—minutes (1m = 60s);
  - *s* or no suffix—seconds.

If the time interval is specified in seconds, you can specify milliseconds after a point (but no more than three digits after the separator, for example, 0.5s—500 milliseconds). It is possible to specify several time intervals in different time units. In this case, the resulting interval is counted as a sum of intervals (in fact, a time interval is always converted to milliseconds before the value is written to configuration).

In general terms, any time an interval can be represented as an expression of this form:  $N_1wN_2dN_3hN_4mN_5[N_6]s$ , where  $N_1, \dots, N_6$  is a number of corresponding time unites included in this interval. For example, a year (365 days) can be represented as follows (all records are equal): 365d, 52w1d, 52w24h, 51w7d24h, 51w7d23h60m, 8760h, 525600m, 31536000s.

The examples below show you how intervals of 30 minutes, 2 seconds, 500 milliseconds can be specified:

1) in the configuration file:

```
UpdateInterval = 30m2.5s
```

2) using the `drweb-ctl cfset` [command](#):

```
# drweb-ctl cfset Update.UpdateInterval 1802.5s
```

3) via a command-line parameter (for example, for [Command-Line Arguments](#)):

```
$ drweb-se --WatchdogInterval 1802.5
```



- **size**—parameter value can be the size of an object (file, buffer, cache, and so on), consisting of a non-negative integer and a suffix, which stands for a unit. The following suffixes can be used:

- **mb**—megabytes (1mb = 1024kb);
- **kb**—kilobytes (1kb = 1024b);
- **b**—bytes.

If the suffix is omitted, the size is considered as in bytes. It is possible to specify several sizes in different units. In this case, the resulting size is counted as their sum (in fact, a size value is always converted to bytes);

- **path to a directory (file)**—parameter value can be a string, which is a path to a directory (file).



The file path must be ended with the file name.



In UNIX-like systems, names of directories and files are case sensitive. If it is not explicitly designated in a parameter description, paths cannot contain masks with special characters (?, \*).

- **logging level**—the level at which the Dr.Web Industrial for UNIX File Servers component events are logged. The following values are possible:
  - **DEBUG**—the most detailed logging level. All messages and debug information are registered;
  - **INFO**—all messages are registered;
  - **NOTICE**—all error messages, warnings, and notifications are registered;
  - **WARNING**—all error messages and warnings are registered;
  - **ERROR**—only error messages are registered;
- **log type**—parameter value defines how the Dr.Web Industrial for UNIX File Servers component performs logging (its logging method). The following values are possible:
  - **Stderr[:ShowTimestamp]**—messages are displayed in the *stderr*—standard error stream. This value can be used *only* in the settings of configuration daemon. At that, if it works in background mode ("*daemonized*"), i.e. it is launched with the parameter `-d` specified, this value *cannot* be used because components operating in the background mode cannot access I/O streams of the terminal). The additional parameter *ShowTimestamp* instructs to add a time stamp to every message;
  - **Auto**—messages for logging are sent to the configuration daemon Dr.Web ConfigD, which saves them to one location according to its configuration (the parameter *Log* in the *[Root]* section). This value is specified for all components *except for the configuration daemon* and is used as a default value;
  - **Syslog[:<facility>]**—messages are transmitted to the system logging service *syslog*;



- additional option *<facility>* is used to specify a level at which `syslog` registers messages. The following values are possible:
  - `DAEMON`—messages of daemons,
  - `USER`—messages of user processes,
  - `MAIL`—messages of mail programs,
  - `LOCAL0`—messages of local processes 0,
  - ...
  - `LOCAL7`—messages of local processes 7;
- *<path>*—Messages are to be saved directly to the specified log.

Example of how to specify the parameter value:

1) in the configuration file:

```
Log = Stderr:ShowTimestamp
```

2) using the `drweb-ctl cfset` [command](#):

```
# drweb-ctl cfset Root.Log /var/opt/drweb.com/log/general.log
```

3) via a command-line parameter (for example, for the [Command-Line Arguments](#)):

```
$ drweb-se --Log Syslog:DAEMON
```

- *action*—action performed by the Dr.Web Industrial for UNIX File Servers component upon detection of certain threats or upon another event. The following values are possible:
  - `Report`—instructs only to notify on threat detection without performing any other action;
  - `Block`—instructs to block all attempts to access the infected file without modifying it (the action might not be available for all components);
  - `Cure`—instructs to attempt to cure the threat (that is, remove only malicious content);
  - `Quarantine`—instructs to move the infected file to quarantine;
  - `Delete`—instructs to delete the infected file.



Some of the actions can be applied only upon certain events (for example, a “scanning error” event cannot trigger the `Cure` action). Allowed actions are always listed in the parameter description of the *action* type.

Other parameter types and their possible values are specified in the description of these parameters.



## Appendix E. Generating SSL certificates

For the Dr.Web Industrial for UNIX File Servers components that use a secure SSL/TLS data channel and application protocols, such as HTTPS, LDAPS, SMTPS, and so on, it is necessary to provide private SSL keys and the corresponding certificates. Keys and certificates for some components are generated automatically; and for others—they should be provided by the Dr.Web Industrial for UNIX File Servers user. All the components use certificates in the PEN format.

To generate private keys and certificates used for connections via SSL/TLS, including verification certificates of Certification Authority (CA) and signed certificates, you can use the command-line utility `openssl` (included in an OpenSSL cryptographic package).

Consider sequence of actions required for generating a private key and the corresponding SSL certificate together with a SSL certificate signed by the CA verification certificate.

### To Generate a Private SSL Key and a Certificate

1. To generate a private key (the RSA algorithm, the key length is 2048 bits), execute the command:

```
$ openssl genrsa -out keyfile.key 2048
```

If you want to password-protect the key, use the `-des3` option. The generated key is in the file `keyfile.key` located in the current directory.

To view the key, use the command:

```
$ openssl rsa -noout -text -in keyfile.key
```

2. To generate a certificate for the specified time period, based on the existing private key (in this case, for 365 days), execute the command:

```
$ openssl req -new -x509 -days 365 -key keyfile.key -out certificate.crt
```



Note that this command will request data (name, organization, and so on) that should identify the certifying object. The generated certificate will be located into the file `certificate.crt`.

To scan the contents of the generated certificate, use the command:

```
$ openssl x509 -noout -text -in certificate.crt
```

### To Register a Certificate as a Trusted CA Certificate

1. Move or copy the certificate file to the system trusted certificate directory (`/etc/ssl/certs/` in Debian/Ubuntu).



2. In the trusted certificate directory, create a symbolic link to the certificate, where the name of the link is the hash value of the certificate.
3. Reindex the contents of the system directory containing certificates.

The example below performs all these three actions. This assumes that the current certificate directory is the trusted certificates directory `/etc/ssl/certs/` and the certificate that is registered as a trusted one is located in the `/home/user/ca.crt` file:

```
# cp /home/user/ca.crt ./
# ln -s ca.crt `openssl x509 -hash -noout -in ca.crt`.0
# c_rehash /etc/ssl/certs/
```

### To create a signed certificate

1. Generate a request for signing a certificate (*Certificate Signing Request, CSR*) based on the existing private key. If the key is absent, generate it.

The request for signing is created with the command:

```
$ openssl req -new -key keyfile.key -out request.csr
```

This command, as well as the command responsible for certificate creation, requests data that should identify the certified object. `keyfile.key` here is the existing file of the private key. The received request will be saved to the file `request.csr`.

To check the result of request creation, use the command:

```
$ openssl req -noout -text -in request.csr
```

2. Create a signed certificated, based on the request and the existing CA certificate, by using the command:

```
$ openssl x509 -req -days 365 -CA ca.crt -CAkey ca.key -set_serial 01 -in request.csr -out sigcert.crt
```



To create a signed certificate, you must have the following three files: the file of the root certificate `ca.crt` and its private key `ca.key` (the `certificate.crt` certificate and the `keyfile.key` key may be used instead of `ca.crt` and `ca.key`, then the obtained certificate will be self-signed), as well as the request for signing `request.csr`. The created signed certificate will be saved to the file `sigcert.crt`.

Use the following command to check the result:

```
$ openssl x509 -noout -text -in sigcert.crt
```

Repeat this procedure as many times as unique certificates you want to create. For example, every agent for distributed file scanning Dr.Web Network Checker within a scanning cluster should have its own key and certificate.





## Modifying a signed certificate

Some browsers or mail clients may require modification of the signed certificate, used for authorization, to the PKCS12 format.

You can modify the certificate using the command:

```
# openssl pkcs12 -export -in sigcert.crt -out sigcert.pfx -inkey keyfile.key
```

`Sigcert.crt` here is an existing file of the signed certificate. `keyfile.key` is a file of the corresponding private key. The modified certificate is saved to `sigcert.pfx`.



## Appendix F. Known Errors

### In this appendix

- [Recommendations for Error Identification](#)
- [Error Codes](#)
- [Errors without Code](#)



If you encounter an error that is not described in this section, please contact [technical support](#). Be ready to name the error code and describe steps to reproduce the issue.

### Recommendations for Error Identification

- To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the following [command](#):

```
# drweb-ctl log
```

- To identify the error, we recommend you to configure logging to a separate file and enable output of extended information to the log. For that, run the following [commands](#):

```
# drweb-ctl cfset Root.Log <path to log file>
# drweb-ctl cfset Root.DefaultLogLevel DEBUG
```

- To return to the default logging method and verbosity level, execute the commands:

```
# drweb-ctl cfset Root.Log -r
# drweb-ctl cfset Root.DefaultLogLevel -r
```

### Errors Codes

**Error message:** *Error on monitor channel*

**Error code:** x1

**Internal designation:** EC\_MONITOR\_IPC\_ERROR

**Description:** One or several components cannot connect with the [Dr.Web ConfigD](#) configuration daemon.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.



### Resolving the error

1. Restart the configuration daemon by executing the command:

```
# service drweb-configd restart
```

2. Check whether the authentication mechanism for PAM is installed, configured and operates correctly. If not so, install and configure it (for details refer to administration guides and manuals for your OS distribution).
3. If PAM is configured correctly and restart of the configuration daemon does not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do this, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the [configuration file](#)), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart the configuration daemon after clearing the contents of the configuration file.

4. If it is not possible to start the configuration daemon, reinstall the `drweb-configd` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Operation is already in progress*

**Error code:** `x2`

**Internal designation:** `EC_ALREADY_IN_PROGRESS`

**Description:** The operation is already in progress.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Wait until operation is finished. If necessary, repeat the required action later.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Operation is in pending state*

**Error code:** `x3`

**Internal designation:** `EC_IN_PENDING_STATE`

**Description:** The requested operation is in pending state.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for



UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Wait for the operation to start. If necessary, repeat the required action later.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Interrupted by user*

**Error code:** `x4`

**Internal designation:** `EC_INTERRUPTED_BY_USER`

**Description:** The action has been terminated by the user.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action later.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Operation canceled*

**Error code:** `x5`

**Internal designation:** `EC_CANCELED`

**Description:** The action has been canceled.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action later.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *IPC connection terminated*

**Error code:** `x6`

**Internal designation:** `EC_LINK_DISCONNECTED`

**Description:** An inter-process communication (IPC) connection with one of the Dr.Web Industrial for UNIX File Servers components has terminated. It must have shut down after being idle for a long time.



To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. If the operation is not finished, repeat it later. Otherwise, the termination is not an error.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid IPC message size*

**Error code:** `x7`

**Internal designation:** `EC_BAD_MESSAGE_SIZE`

**Description:** A message of invalid size has been received during component inter-process communication (IPC).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Reload Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid IPC message format*

**Error code:** `x8`

**Internal designation:** `EC_BAD_MESSAGE_FORMAT`

**Description:** A message of invalid format has been received during component inter-process communication (IPC).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Reload Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Not ready*

**Error code:** x9

**Internal designation:** EC\_NOT\_READY

**Description:** The required action cannot be performed because the necessary component or device has not been initialized yet.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action later.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Component is not installed*

**Error code:** x10

**Internal designation:** EC\_NOT\_INSTALLED

**Description:** The required operation cannot be performed because the necessary component has not been installed yet.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Install or reinstall the necessary component. If you do not know the component name, try to determine it reviewing the log file.
2. If the installation or reinstallation of the necessary component does not help, reinstall Dr.Web Industrial for UNIX File Servers.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unexpected IPC message*

**Error code:** x11

**Internal designation:** EC\_UNEXPECTED\_MESSAGE

**Description:** An unexpected message is received during component inter-process communication (IPC).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Reload Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *IPC protocol violation*

**Error code:** x12

**Internal designation:** EC\_PROTOCOL\_VIOLATION

**Description:** Protocol violation has occurred during component inter-process communication (IPC).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Reload Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Subsystem state is unknown*

**Error code:** x13

**Internal designation:** EC\_UNKNOWN\_STATE

**Description:** The required operation cannot be performed because one or more subsystems of Dr.Web Industrial for UNIX File Servers are in unknown state.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Repeat the operation.
2. If the error persists, restart Dr.Web Industrial for UNIX File Servers by executing the command:

```
# service drweb-configd restart
```

and then repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Path must be absolute*

**Error code:** x20

**Internal designation:** EC\_NOT\_A\_DIRECTORY

**Description:** A relative path to a file or directory is specified whereas an absolute path is required.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Change the path to the file or directory so as to make the path absolute.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Not enough memory*

**Error code:** x21

**Internal designation:** EC\_NO\_MEMORY

**Description:** There is not enough memory to complete the requested operation.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Increase size of available memory for Dr.Web Industrial for UNIX File Servers processes (for example, by changing the limits with the `ulimit` command), restart Dr.Web Industrial for UNIX File Servers and repeat the operation.



In some cases, the system service `systemd` can ignore the specified limit changes. In this case, edit (or create if it does not exist) a file `/etc/systemd/system/drweb-configd.service.d/limits.conf` and specify the changed limit value, for example:

```
[Service]
LimitDATA=32767
```

The list of available limits of `systemd` can be viewed in the documentation `man systemd.exec`.

Restart Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *I/O error*





**Error code:** x22

**Internal designation:** EC\_IO\_ERROR

**Description:** An input/output (I/O) error has occurred.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check whether the required I/O device or the partition of the file system is available. If necessary, mount it and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *No such file or directory*

**Error code:** x23

**Internal designation:** EC\_NO\_SUCH\_ENTRY

**Description:** The specified object of the file system (file or directory) is missing. It may have been removed.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the path. If necessary, change it and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Permission denied*

**Error code:** x24

**Internal designation:** EC\_PERMISSION\_DENIED

**Description:** The component cannot access the specified file or directory. It may not have the required permission to access the item.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check whether the path is correct and whether the component has the required permissions. If it is necessary to access the object, change access permissions or elevate component permissions. Repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Not a directory*

**Error code:** x25

**Internal designation:** EC\_NOT\_A\_DIRECTORY

**Description:** The specified object of the file system is not a directory.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the path. Specify the correct path and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Data file corrupted*

**Error code:** x26

**Internal designation:** EC\_NOT\_A\_DIRECTORY

**Description:** The requested data is corrupted.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the operation.
2. If the error persists, restart Dr.Web Industrial for UNIX File Servers by executing the command:

```
# service drweb-configd restart
```

and then repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *File already exists*

**Error code:** x27

**Internal designation:** EC\_FILE\_EXISTS

**Description:** There is already the file with the same name in the specified location.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check the path. Change it and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Read-only file system*

**Error code:** x28

**Internal designation:** EC\_READ\_ONLY\_FS

**Description:** The file system object (a file, a directory or a socket) that you are trying to modify is read-only.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check the path. Change it so that the path indicates the writable partition of the file system and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Network error*

**Error code:** x29

**Internal designation:** EC\_NETWORK\_ERROR

**Description:** A network error has occurred.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check whether the network is available and network settings are correct. If necessary, change network settings and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Not a drive*

**Error code:** x30

**Internal designation:** EC\_NOT\_A\_DRIVE

**Description:** The I/O device being accessed is not a drive.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for



UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the device name. Change the path so that it indicate to the drive and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unexpected EOF*

**Error code:** `x31`

**Internal designation:** `EC_UNEXPECTED_EOF`

**Description:** The end of file has been reached unexpectedly when reading data.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the name of the file. If necessary, change the path so that it indicates the correct file and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *File was changed*

**Error code:** `x32`

**Internal designation:** `EC_FILE_WAS_CHANGED`

**Description:** The file being scanned has been modified.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat scanning.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Not a regular file*

**Error code:** `x33`

**Internal designation:** `EC_NOT_A_REGULAR_FILE`

**Description:** The object being accessed is not a regular file (it may a directory, a socket, etc.).



To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the name of the file. If necessary, change the path so that it indicates the regular file and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Name already in use*

**Error code:** `x34`

**Internal designation:** `EC_NAME_ALREADY_IN_USE`

**Description:** The object cannot be created as there is an object with the same name in the file system.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the path. Change it and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Host is offline*

**Error code:** `x35`

**Internal designation:** `EC_HOST_OFFLINE`

**Description:** A remote host cannot be accessed via the network.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check whether the required host is available. If necessary, change the host address and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Resource limit reached*

**Error code:** `x36`

**Internal designation:** `EC_LIMIT_REACHED`



**Description:** The limit defined for the use of a certain resource has been reached.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the availability of the required resource. If necessary, raise the limit on the use of this resource and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Different mount points*

**Error code:** `x37`

**Internal designation:** `EC_CROSS_DEVICE_LINK`

**Description:** The file cannot be restored as restoring implies moving it between two different mountain points.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Choose another path for the file restoration and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unpacking error*

**Error code:** `x38`

**Internal designation:** `EC_UNPACKING_ERROR`

**Description:** Archive unpacking failed.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Make sure that the archive is not corrupted. If the archive is protected with password, remove the protection by entering the correct password and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Virus database corrupted*



**Error code:** x40

**Internal designation:** EC\_BASE\_CORRUPTED

**Description:** Virus databases are corrupted.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the virus database directory. Change the path, if necessary (the `VirusBaseDir` parameter in the [Root] [section](#) of the [configuration file](#)).
  - To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.VirusBaseDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir -r
```

2. Update virus databases:
  - click **Update** on the **Main** page of the [web interface](#), if installed;
  - or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Non-supported virus database version*

**Error code:** x41

**Internal designation:** EC\_OLD\_BASE\_VERSION

**Description:** Current virus databases are designed for an earlier program version.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the virus database directory. Change the path, if necessary (the `VirusBaseDir` parameter in the [Root] [section](#) of the [configuration file](#)).
  - To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.



- You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.VirusBaseDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir -r
```

## 2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Empty virus database*

**Error code:** x42

**Internal designation:** EC\_EMPTY\_BASE

**Description:** Virus databases are empty.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

## Resolving the error

1. Check the path to the virus database directory. Change the path, if necessary (the `VirusBaseDir` parameter in the `[Root]` [section](#) of the [configuration file](#)).

- To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.
- You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.VirusBaseDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir -r
```





## 2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Object cannot be cured*

**Error code:** x43

**Internal designation:** EC\_CAN\_NOT\_BE\_CURED

**Description:** The **Cure** action has been applied to an incurable object.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Select an action that can be applied to the object and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Non-supported virus database combination*

**Error code:** x44

**Internal designation:** EC\_INVALID\_BASE\_SET

**Description:** The current combination of virus databases cannot be supported.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the virus database directory. Change the path, if necessary (the `VirusBaseDir` parameter in the `[Root]` [section](#) of the [configuration file](#)).
  - To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.VirusBaseDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir <new path>
```



To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir -r
```

2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Scan limit reached*

**Error code:** x45

**Internal designation:** EC\_SCAN\_LIMIT\_REACHED

**Description:** The specified limits have been exceeded during the scanning of the object.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Change limits for scanning (in the component settings) by any of the following methods:
  - on the page with the component settings on the [web interface](#) (if it is installed);
  - use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#).
2. After changing the settings, repeat the previously attempted operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Authentication failed*

**Error code:** x47

**Internal designation:** EC\_AUTH\_FAILED

**Description:** Invalid user credentials have been used for authentication.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Enter valid credentials of the user with the necessary privileges. Try to complete authentication again.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Authorization failed*

**Error code:** x48

**Internal designation:** EC\_NOT\_AUTHORIZED

**Description:** The user does not have enough rights to perform the requested operation.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Enter valid credentials of the user with the necessary privileges. Try to complete authentication again.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Access token is invalid*

**Error code:** x49

**Internal designation:** EC\_INVALID\_TOKEN

**Description:** One of Dr.Web Industrial for UNIX File Servers components provides invalid authorization token on attempt to access the operation, requiring elevated privileges.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Enter valid credentials of the user with the necessary privileges. Try to complete authentication again.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid argument*

**Error code:** x60

**Internal designation:** EC\_INVALID\_ARGUMENT

**Description:** An invalid argument has been used when trying to execute a command.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action again using valid argument.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Invalid operation*

**Error code:** x61

**Internal designation:** EC\_INVALID\_OPERATION

**Description:** An attempt to run an invalid command has been detected.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action again using valid command.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Superuser privileges required*

**Error code:** x62

**Internal designation:** EC\_ROOT\_ONLY

**Description:** Superuser privileges are required to perform the action.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Elevate you privileges to root privileges and repeat the required action. To elevate privileges, you can use the commands `su` and `sudo`.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Not allowed in centralized protection mode*

**Error code:** x63

**Internal designation:** EC\_STANDALONE\_MODE\_ONLY

**Description:** The required action can be performed in standalone [mode](#) only.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Change Dr.Web Industrial for UNIX File Servers operation mode to standalone mode and repeat the operation.
2. To switch Dr.Web Industrial for UNIX File Servers to standalone mode:
  - clear the **Enable centralized protection mode** check box on the **Centralized protection** of the



[web interface](#), if installed;

- or execute the [command](#):

```
# drweb-ctl esdisconnect
```

If the error persists, contact [technical support](#) and be ready to name the error code.

#### **Error message:** *Non-supported OS*

**Error code:** x64

**Internal designation:** EC\_NON\_SUPPORTED\_OS

**Description:** Dr.Web Industrial for UNIX File Servers does not support the operating system installed on the host.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### **Resolving the error**

1. Install the operating system from the list mentioned in [system requirements](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

#### **Error message:** *Feature not implemented*

**Error code:** x65

**Internal designation:** EC\_NOT\_IMPLEMENTED

**Description:** The required features of one or more components are not implemented in the current version.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### **Resolving the error**

1. Restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the [configuration file](#)), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart Dr.Web Industrial for UNIX File Servers after clearing the contents of the configuration file by executing the command:

```
# service drweb-configd restart
```



If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unknown option*

**Error code:** x66

**Internal designation:** EC\_UNKNOWN\_SECTION

**Description:** The [configuration file](#) contains parameters unknown or non-supported in the current version of Dr.Web Industrial for UNIX File Servers.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Open the `<etc_dir>/drweb.ini` file in any text editor, remove the line, containing invalid parameter. Save the file and restart the [Dr.Web ConfigD](#) configuration daemon by executing the command:

```
# service drweb-configd restart
```

2. If it does not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart the configuration daemon after clearing the contents of the configuration file.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unknown section*

**Error code:** x67

**Internal designation:** EC\_UNKNOWN\_SECTION

**Description:** The [configuration file](#) contains sections unknown or non-supported in the current version of Dr.Web Industrial for UNIX File Servers.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Open the `<etc_dir>/drweb.ini` file in any text editor, remove the unknown (non-supported) section. Save the file and restart the [Dr.Web ConfigD](#) configuration daemon by executing the command:

```
# service drweb-configd restart
```



2. If it does not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart the configuration daemon after clearing the contents of the configuration file.

If the error persists, contact [technical support](#) and be ready to name the error code.

#### **Error message:** *Invalid option value*

**Error code:** x68

**Internal designation:** EC\_INVALID\_OPTION\_VALUE

**Description:** One or more parameters in the [configuration file](#) have invalid values.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### **Resolving the error**

1. Set the valid parameter value by any of the following methods:

- on the page with the component settings on the [web interface](#) (if it is installed);
- use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#).

If you do not know which value is valid for the parameter, refer to the help file of the component which uses this parameter. You can also restore parameter value to the default.

2. You can also directly edit the configuration file `<etc_dir>/drweb.ini`. To do this, open the configuration file in any text editor, find the line containing invalid parameter value, set valid value, then save the file and restart the [Dr.Web ConfigD](#) configuration daemon by executing the command:

```
# service drweb-configd restart
```

3. If the previous steps did not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart the configuration daemon after clearing the contents of the configuration file.

If the error persists, contact [technical support](#) and be ready to name the error code.

#### **Error message:** *Invalid state*



**Error code:** x69

**Internal designation:** EC\_INVALID\_STATE

**Description:** Dr.Web Industrial for UNIX File Servers or one of the components is in invalid state to complete the required operation.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Repeat the required action later.
2. If the error persists, restart Dr.Web Industrial for UNIX File Servers by executing the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Only one value allowed*

**Error code:** x70

**Internal designation:** EC\_NOT\_LIST\_OPTION

**Description:** In the [configuration file](#) a list of values is attributed to a single-valued parameter.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Set the valid parameter value by any of the following methods:
  - on the page with the component settings on the [web interface](#) (if it is installed);
  - use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#).

If you do not know which value is valid for the parameter, refer to the help file of the component which uses this parameter. You can also restore parameter value to the default.
2. You can also directly edit the configuration file `<etc_dir>/drweb.ini`. To do this, open the configuration file in any text editor, find the line containing invalid parameter value, set valid value, then save the file and restart the [Dr.Web ConfigD](#) configuration daemon by executing the command:

```
# service drweb-configd restart
```

3. If the previous steps did not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```





Restart the configuration daemon after clearing the contents of the configuration file.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Record not found*

**Error code:** x80

**Internal designation:** EC\_RECORD\_NOT\_FOUND

**Description:** The threat record is missing (it may have already been processed by another Dr.Web Industrial for UNIX File Servers component).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Update the threat list after some time.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Record is in process now*

**Error code:** x81

**Internal designation:** EC\_RECORD\_BUSY

**Description:** The record is already being processed by another component.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Update the threat list after some time.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *File has already been quarantined*

**Error code:** x82

**Internal designation:** EC\_RECORD\_BUSY

**Description:** On attempt to move the file with the detected threat to quarantine, it is found out that the file is already in quarantine (most likely, another component processed the threat).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Update the threat list after some time.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Update zone is not provided on disk*

**Error code:** x84

**Internal designation:** EC\_NO\_ZONE\_ON\_DISK

**Description:** The attempt to update the virus bases in the offline mode turned unsuccessful.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Make sure that the path to the device used for updating is correct.
2. Make sure that the user under which you try to update the bases has enough read permissions on the directory containing the updates.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Cannot backup before update*

**Error code:** x89

**Internal designation:** EC\_BACKUP\_FAILED

**Description:** Prior to downloading the updates from the updates server, an attempt to make a backup copy of the files to be updated failed.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check the path to the directory that stores backup copies of the files that are updated. Change the path, if necessary (the `BackupDir` parameter in the [Update] [section](#) of the [configuration file](#)).
  - To view and change the path, go to the **Updater** page of the [web interface](#) (if it is installed).
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Update.BackupDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Update.BackupDir <new path>
```



To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Update.BackupDir -r
```

2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

3. If the error persists, check whether the user under whose account the Dr.Web Updater component is running has a write permission to the directory specified in the `BackupDir`. The name of this user is specified in the `RunAsUser` parameter. If necessary, change the user specified in the `RunAsUser` parameter or grant the missing permissions in the directory properties.
4. If the error persists, reinstall the `drweb-update` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid DRL file*

**Error code:** x90

**Internal designation:** EC\_BAD\_DRL\_FILE

**Description:** The integrity of one of the files with the list of update servers has been violated.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check the path to the file with the list of servers and change the path if necessary (parameters with `*DrlDir` in [section \[Update\] of configuration file](#)).

- To view and change the path, go to the **Updater** page of the [web interface](#) (if it is installed).
- You also can use the [commands](#) of the command-line management tool.

To view the current parameter value, use the command (`<*DrlDirPath>` needs to be substituted with a specified parameter name. If the parameter name is unclear, refer to all parameter values in the section, skipping the command part in square brackets):

```
$ drweb-ctl cfshow Update[.<*DrlDir>]
```

To set new parameter value, execute the command (`<*DrlDir>` needs to be substituted with a specified parameter name):

```
# drweb-ctl cfset Update.<*DrlDir> <new path>
```



To restore parameter value to the default, execute the command (<\*DrDir> needs to be substituted with a specified parameter name):

```
# drweb-ctl cfset Update.<*DrDir> -r
```

2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

3. If the error persists, reinstall the drweb-update package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid LST file*

**Error code:** x91

**Internal designation:** EC\_BAD\_LST\_FILE

**Description:** The integrity of the file with the list of updated virus databases has been violated.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Update virus databases again after some time:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

2. If the error persists, reinstall the drweb-update package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid compressed file*

**Error code:** x92

**Internal designation:** EC\_BAD\_LZMA\_FILE



**Description:** An integrity violation of the downloaded file containing updates has been detected.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Update virus databases again after some time:
  - click **Update** on the **Main** page of the [web interface](#), if installed;
  - or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Proxy authentication error*

**Error code:** x93

**Internal designation:** EC\_PROXY\_AUTH\_ERROR

**Description:** The program fails to connect to update servers via the proxy server specified in the settings.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the parameters used to connect to a proxy server (they are set in the `Proxy` parameter in the [Update] [section](#) of the [configuration file](#)).
  - To view and set the connection parameters, go to the **Updater** page of the [web interface](#) (if it is installed).
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Update.Proxy
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Update.Proxy <new parameters>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Update.Proxy -r
```

2. Update virus databases:
  - click **Update** on the **Main** page of the [web interface](#), if installed;



- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *No update servers available*

**Error code:** x94

**Internal designation:** EC\_NO\_UPDATE\_SERVERS

**Description:** The program fails to connect to any of the update servers.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check whether the network is available. Change network settings, if necessary.
2. If you can access the network only using a proxy server, set parameters to connect to the proxy server (you can set them in the `Proxy` parameter in the `[Update]` [section](#) of the [configuration file](#)).
  - To view and set the connection parameters, go to the **Updater** page of the [web interface](#) (if it is installed).
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Update.Proxy
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Update.Proxy <new parameters>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Update.Proxy -r
```

3. If network connection parameters (including parameters of proxy server) are correct, but the error occurs, make sure you use the available list of update servers. The list of update servers used is displayed in parameters `*Dr1Dir` in `[Update]` section of configuration file.



If parameters `*CustomDr1Dir` indicate the existing correct file of servers list, the servers specified there will be used instead of the servers of the standard update zone (the value specified in the corresponding parameter `*Dr1Dir`, is ignored).

- To view and set the connection parameters, go to the **Updater** page of the [web interface](#) (if it is installed).
- You also can use the [commands](#) of the command-line management tool.



To view the current parameter value, use the command (<*DrIDirPath*> needs to be substituted with a specified parameter name. If the parameter name is unclear, refer to all parameter values in the section, skipping the command part in square brackets):

```
$ drweb-ctl cfshow Update[.<*DrIDir>]
```

To set new parameter value, execute the command (<*DrIDir*> needs to be substituted with a specified parameter name):

```
# drweb-ctl cfset Update.<*DrIDir> <new path>
```

To restore parameter value to the default, execute the command (<*DrIDir*> needs to be substituted with a specified parameter name):

```
# drweb-ctl cfset Update.<*DrIDir> -r
```

#### 4. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

#### Error message: *Invalid key file format*

**Error code:** x95

**Internal designation:** EC\_BAD\_KEY\_FORMAT

**Description:** The key file format is violated.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check whether you have the key file and the path to it. You can specify the path to the key file in the `KeyPath` parameter in the [Root] [section](#) of the [configuration file](#).
  - To view and set the path to the key file, go to the **General Settings** page of the [web interface](#), if installed.
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.KeyPath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.KeyPath <path to file>
```



To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.KeyPath -r
```

2. If you do not have the key file or the used key file is corrupted, purchase and install it. For more details on the key file, purchase and installation refer to section [Licensing](#).
3. To install the key file, you can use the license activation form at the bottom of the **Main** page of the [web interface](#), if installed.
4. You can view current license options on user webpage **My Dr.Web** at <https://support.drweb.com/get+cabinet+link/>.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *License is already expired*

**Error code:** x96

**Internal designation:** EC\_EXPIRED\_KEY

**Description:** The license has expired.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Purchase a new license and install the key file that you will receive. For more details on ways to purchase the license and installation of the key file refer to section [Licensing](#).
2. To install the purchased key file, you can use the license activation form at the bottom of the **Main** page of the [web interface](#), if installed.
3. You can view current license options on user webpage **My Dr.Web** at <https://support.drweb.com/get+cabinet+link/>.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Network operation timed out*

**Error code:** x97

**Internal designation:** EC\_NETWORK\_TIMEOUT

**Description:** Network operation timed out (possibly, a remote host stops responding unexpectedly or the required connection fails).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check whether the network is available and network settings are correct. If necessary, change





network settings and repeat the operation.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid checksum*

**Error code:** x98

**Internal designation:** EC\_BAD\_CHECKSUM

**Description:** The checksum of the downloaded file with updates is corrupted.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Update virus databases again after some time:
  - click **Update** on the **Main** page of the [web interface](#), if installed;
  - or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid trial license*

**Error code:** x99

**Internal designation:** EC\_BAD\_TRIAL\_KEY

**Description:** The demo key file is invalid (for example, it may have been received from another computer).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Send a request for a new demo period for this computer or purchase a new license and install a key file that you will receive. For more details on ways to purchase the license and installation of the key file refer to section [Licensing](#).
2. To install the purchased key file, you can use the license activation form at the bottom of the **Main** page of the [web interface](#), if installed.
3. You can view current license options on user webpage **My Dr.Web** at <https://support.drweb.com/get+cabinet+link/>.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Blocked license key*

**Error code:** x100

**Internal designation:** EC\_BLOCKED\_LICENSE

**Description:** The license in use is blocked (the terms of use of Dr.Web Industrial for UNIX File Servers may be violated).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Purchase a new license and install a key file that you will receive. For more details on ways to purchase the license and installation of the key file refer to section [Licensing](#).
2. To install the received key file, you can use the license activation form at the bottom of the **Main** page of the [web interface](#), if installed.
3. You can view current license options on user webpage **My Dr.Web** at <https://support.drweb.com/get+cabinet+link/>.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid license*

**Error code:** x101

**Internal designation:** EC\_BAD\_LICENSE

**Description:** The license is designed for other product or does not allow the operation of Dr.Web Industrial for UNIX File Servers components.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Purchase a new license and install the key file that you will receive. For more details on ways to purchase the license and installation of the key file refer to section [Licensing](#).
2. To install the received key file, you can use the license activation form at the bottom of the **Main** page of the [web interface](#), if installed.
3. You can view current license options on the user webpage **My Dr.Web** at <https://support.drweb.com/get+cabinet+link/>.

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid configuration*

**Error code:** x102

**Internal designation:** EC\_BAD\_CONFIG



**Description:** One or more Dr.Web Industrial for UNIX File Servers components cannot operate because of incorrect configuration settings.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. If you do not know the name of the component which causes the error, try to determine it by reviewing the log file.
2. If the error is reported by the SpIDer Guard component, the mode which is selected for the component operation is not probably supported by the OS. Check the selected mode and change it, if necessary. You can do it by setting the value `AUTO` (the `Mode` parameter in the `[LinuxSpider]` section of the [configuration file](#)).
  - To view and change the mode, go to the **SpIDer Guard** page of the [web interface](#) (if it is installed).
  - You also can use the [commands](#) of the command-line management tool.

To set the value to `AUTO`, execute the command:

```
# drweb-ctl cfset LinuxSpider.Mode AUTO
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset LinuxSpider.Mode -r
```

3. If the error is reported by another component, restore component settings to the defaults by any of the following methods:
  - on the page with the component settings on the [web interface](#) (if it is installed);
  - use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#);
  - edit the [configuration file](#) manually (delete all parameters from the component section).
4. If the previous steps did not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save  
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart Dr.Web Industrial for UNIX File Servers after clearing the contents of the configuration file by executing the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Invalid executable file*

**Error code:** `x104`



**Internal designation:** EC\_BAD\_EXECUTABLE

**Description:** The executable file of the component is corrupted.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. If you do not know the name of the component which causes the error, try to determine it by reviewing the log file.
2. Check the executable path to the component in the Dr.Web Industrial for UNIX File Servers configuration file (the `ExePath` parameter in the component section), by executing the following [command](#) (change `<component section>` for the name of the corresponding section of the [configuration file](#)):

```
$ drweb-ctl cfshow <component section>.ExePath
```

3. Restore the path to the default by executing the following command (change `<component section>` for the name of the corresponding section of the configuration file):

```
# drweb-ctl cfset <component section>.ExePath -r
```

4. If the previous steps do not help, reinstall the package of the corresponding component.  
For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Core engine is not available*

**Error code:** x105

**Internal designation:** EC\_NO\_CORE\_ENGINE

**Description:** The file of Dr.Web Virus-Finding Engine is missing or unavailable (required for threat detection).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Check the path to the `drweb32.dll` scan engine file. Change the path, if necessary (the `CoreEnginePath` parameter in the `[Root]` [section](#) of the [configuration file](#)).
  - To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.
  - You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.CoreEnginePath
```



To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.CoreEnginePath <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.CoreEnginePath -r
```

2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

3. If the path is correct and the error persists after updating virus databases, reinstall the drweb-bases package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *No virus databases*

**Error code:** x106

**Internal designation:** EC\_NO\_VIRUS\_BASES

**Description:** Virus databases have not been found.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

**Resolving the error**

1. Check the path to the virus database directory. Change the path, if necessary (the `VirusBaseDir` parameter in the `[Root]` [section](#) of the [configuration file](#)).

- To view and change the path, go to the **General Settings** page of the [web interface](#), if installed.
- You also can use the [commands](#) of the command-line management tool.

To view current parameter value, execute the command:

```
$ drweb-ctl cfshow Root.VirusBaseDir
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Root.VirusBaseDir -r
```



## 2. Update virus databases:

- click **Update** on the **Main** page of the [web interface](#), if installed;
- or execute the [command](#):

```
$ drweb-ctl update
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Process terminated by signal*

**Error code:** x107

**Internal designation:** EC\_APP\_TERMINATED

**Description:** A component has shut down (e.g., because of the user command or being idle).

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. If the operation is not finished, start it again. Otherwise, the shutdown is not an error.
2. If a component shuts down constantly, restore its settings to the defaults by any of the following methods:
  - on the page with the component settings on the [web interface](#) (if it is installed);
  - use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#);
  - edit the [configuration file](#) manually (delete all parameters from the component section).
3. If it did not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart Dr.Web Industrial for UNIX File Servers after clearing the contents of the configuration file by executing the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Unexpected process termination*

**Error code:** x108

**Internal designation:** EC\_APP\_CRASHED

**Description:** A component has shut down because of failure.



To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Repeat the terminated operation.
2. If the component constantly shuts down abnormally, restore its settings to the defaults by any of the following methods:
  - on the page with the component settings on the [web interface](#) (if it is installed);
  - use the `drweb-ctl cfshow` and `drweb-ctl cfset` [commands](#);
  - edit the [configuration file](#) manually (delete all parameters from the component section).
3. If it did not help, restore Dr.Web Industrial for UNIX File Servers settings to the defaults.

To do it, clear the contents of the `<etc_dir>/drweb.ini` file (it is recommended that you make a backup of the configuration file), for example, by executing the following commands:

```
# cp /etc/opt/drweb.com/drweb.ini /etc/opt/drweb.com/drweb.ini.save
# echo "" > /etc/opt/drweb.com/drweb.ini
```

Restart Dr.Web Industrial for UNIX File Servers after clearing the contents of the configuration file by executing the command:

```
# service drweb-configd restart
```

4. If the error persists after restoring Dr.Web Industrial for UNIX File Servers settings, reinstall the component package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *Incompatible software detected*

**Error code:** `x109`

**Internal designation:** `EC_INCOMPATIBLE`

**Description:** One or several components of Dr.Web Industrial for UNIX File Servers cannot operate properly. There is software that impedes their operation in your system.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Disable or reconfigure the incompatible software so as to prevent any interference with the Dr.Web Industrial for UNIX File Servers operation.

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *MeshD is not available*

**Error code:** x114

**Internal designation:** EC\_NO\_MESH D

**Description:** The Dr.Web MeshD component required for load balancing during the scanning of files is missing.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the `drweb-meshd` executable file. Change the path, if necessary (the `ExePath` parameter in the [MeshD] [section](#) of the [configuration file](#)).

You can use the [commands](#) of the command-line management tool.

To view the current parameter value, execute the command:

```
$ drweb-ctl cfshow MeshD.ExePath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset MeshD.ExePath <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset MeshD.ExePath -r
```

2. If the configuration does not contain the settings for Dr.Web MeshD component or if the error persists after entering the correct path, install or reinstall the `drweb-meshd` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *ScanEngine is not available*

**Error code:** x119

**Internal designation:** EC\_NO\_SCAN\_ENGINE

**Description:** Dr.Web Scanning Engine component required for threat detection is missing or failed to start.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.





### Resolving the error

1. Check the path to the `drweb-se` executable file. Change the path, if necessary (the `ExePath` parameter in the `[ScanEngine]` [section](#) of the [configuration file](#)).

You can use the [commands](#) of the command-line management tool.

To view the current parameter value, execute the command:

```
$ drweb-ctl cfshow ScanEngine.ExePath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset ScanEngine.ExePath <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset ScanEngine.ExePath -r
```

2. If the error persists after entering the correct path,

- Execute the command:

```
$ drweb-ctl rawscan /
```

If the line "Error: No valid license provided" is output, a valid key file is missing. Register Dr.Web Industrial for UNIX File Servers and receive a license. After receiving the license, check whether the [key file](#) is available and install it, if necessary.

- If your operating system uses SELinux, configure the security policy for the `drweb-se` module (see section [Configuring SELinux Security Policies](#)).

3. If the configuration does not contain the Dr.Web Scanning Engine component settings or if the steps previously mentioned do not help, install or reinstall the `drweb-se` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *FileCheck is not available*

**Error code:** `x120`

**Internal designation:** `EC_NO_FILE_CHECK`

**Description:** Dr.Web File Checker component required for threat detection is missing or failed to start.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the `drweb-filecheck` executable file. Change the path, if necessary (the `ExePath` parameter in the `[FileCheck]` [section](#) of the [configuration file](#)).



You can use the [commands](#) of the command-line management tool.

To view the current parameter value, execute the command:

```
$ drweb-ctl cfshow FileCheck.ExePath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset FileCheck.ExePath <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset FileCheck.ExePath -r
```

2. If the error persists after entering the correct path,
  - If your operating system uses SELinux, configure the security policy for the `drweb-filecheck` module (see section [Configuring SELinux Security Policies](#)).
3. If the configuration does not contain the Dr.Web File Checker component settings or if the steps previously mentioned do not help, install or reinstall the `drweb-filecheck` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *ESAgent is not available*

**Error code:** `x121`

**Internal designation:** `EC_NO_ESAGENT`

**Description:** Dr.Web ES Agent component necessary to connect to the centralized protection server is missing.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the `drweb-esagent` executable file. Change the path, if necessary (the `ExePath` parameter in the `[ESAgent]` [section](#) of the [configuration file](#)).

You can use the [commands](#) of the command-line management tool.

To view the current parameter value, execute the command:

```
$ drweb-ctl cfshow ESAgent.ExePath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset ESAgent.ExePath <new path>
```



To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset ESAgent.ExePath -r
```

2. If the configuration does not contain settings for the Dr.Web ES Agent component or if the error persists after entering the correct path, install or reinstall the `drweb-esagent` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.

**Error message:** *NetChecker is not available*

**Error code:** x123

**Internal designation:** EC\_NO\_NET\_CHECK

**Description:** Dr.Web Network Checker component required for scanning the downloaded files is missing.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

### Resolving the error

1. Check the path to the `drweb-netcheck` executable file. Change the path, if necessary (the `ExePath` parameter in the [Netcheck] [section](#) of the [configuration file](#)).

You can use the [commands](#) of the command-line management tool.

To view the current parameter value, execute the command:

```
$ drweb-ctl cfshow Netcheck.ExePath
```

To set a new parameter value, execute the command:

```
# drweb-ctl cfset Netcheck.ExePath <new path>
```

To restore the parameter value to the default, execute the command:

```
# drweb-ctl cfset Netcheck.ExePath -r
```

2. If the configuration does not contain settings for the Dr.Web Network Checker component or if the error persists after entering the correct path, install or reinstall the `drweb-netcheck` package.

For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#) and be ready to name the error code.



**Error message:** *Unexpected error*

**Error code:** x125

**Internal designation:** EC\_UNEXPECTED\_ERROR

**Description:** An unexpected error has occurred in operation of one of the components.

To identify the possible cause and the circumstances of the error, refer to the Dr.Web Industrial for UNIX File Servers log (by default, it is located in the `/var/log/syslog` file or the `/var/log/messages` file, depending on OS). Also, you can use the [command](#) `drweb-ctl log`.

#### Resolving the error

1. Restart Dr.Web Industrial for UNIX File Servers by entering the command:

```
# service drweb-configd restart
```

If the error persists, contact [technical support](#) and be ready to name the error code.

## Errors Without Code

**Symptoms:** The web browser cannot establish connection to Dr.Web management web interface; the components of Dr.Web anti-virus solutions are not in the list of running processes (`ps ax | grep drweb`); attempt to execute any `drweb-ctl <command>`, except for `drweb-ctl rawscan`, results in one of the following errors:

Error: connect: No such file or directory: "`<path>/com.drweb.public`"  
or

Error: connect: Connection refused: "`<path>/com.drweb.public`".

**Description:** Dr.Web Industrial for UNIX File Servers cannot start as the configuration daemon Dr.Web ConfigD is not available.

#### Resolving the error

1. Execute the command:

```
# service drweb-configd restart
```

to restart Dr.Web ConfigD and Dr.Web Industrial for UNIX File Servers.

2. If this command returns an error message, or has no effect, install `drweb-configd` component (package) separately.



Also this may mean that PAM authentication is not used in the system. If so, please install and configure PAM (Dr.Web Industrial for UNIX File Servers cannot operate correctly without PAM).

3. If the error persists, remove Dr.Web Industrial for UNIX File Servers and then install it again.



For details on how to install and uninstall Dr.Web Industrial for UNIX File Servers or its components, refer to sections [Installing Dr.Web Industrial for UNIX File Servers](#) and [Uninstalling Dr.Web Industrial for UNIX File Servers](#).

If the error persists, contact [technical support](#).



## Appendix G. List of Abbreviations

The following abbreviations were used in this manual without further interpretation:

Convention	Complete form
<i>FQDN</i>	Fully Qualified Domain Name
<i>GID</i>	Group ID (system user group identifier)
<i>GNU</i>	GNU project (GNU is Not Unix)
<i>HTML</i>	HyperText Markup Language
<i>HTTP</i>	HyperText Transfer Protocol
<i>HTTPS</i>	HyperText Transfer Protocol Secure (via SSL/TLS)
<i>ID</i>	Identifier
<i>IP</i>	Internet Protocol
<i>MBR</i>	Master Boot Record
<i>OID</i>	(SNMP) Object ID
<i>OS</i>	Operating System
<i>PID</i>	Process ID (system process identifier)
<i>PAM</i>	Pluggable Authentication Modules
<i>RPM</i>	Red Hat Package Manager
<i>RRA</i>	Round-Robin Archive
<i>RRD</i>	Round-Robin Database
<i>SMB</i>	Server Message Block (file access protocol)
<i>SNMP</i>	Simple Network Management Protocol
<i>SP</i>	Service Pack
<i>SSH</i>	Secure Shell
<i>SSL</i>	Secure Sockets Layer
<i>TCP</i>	Transmission Control Protocol
<i>TLS</i>	Transport Layer Security



Convention	Complete form
<i>UID</i>	User ID (system user identifier)
<i>URI</i>	Uniform Resource Identifier
<i>URL</i>	Uniform Resource Locator
<i>VBR</i>	Volume Boot Record



## Index

### A

Abbreviations 318  
About the anti-virus 10  
Activation 59  
Appendices 258  
appendix  
    computer threat types 258  
    fighting computer threats 262

### B

Brief Instructions 69  
Building the VFS SMB Module 150

### C

Centralized protection 21  
Command-line management 80  
Components 12  
computer threats 258  
ConfigD: configuration 77  
Configuration file 266  
Configuration parameters 266  
Configuring CSE 58  
Configuring Security Subsystems 54  
Configuring SELinux 55  
Console uninstaller 43  
Console-based installer 33  
Conventions 9  
Custom Installation 49

### D

Database Update 41  
Dr.Web ConfigD 74  
Dr.Web Ctl 80  
Dr.Web ES Agent 182  
Dr.Web File Checker 153  
Dr.Web HTTPD 186  
Dr.Web License 28  
Dr.Web MeshD 246  
Dr.Web Network Checker 157  
Dr.Web Scanning Engine 168  
Dr.Web SNMP MIB 227  
Dr.Web SNMPD 213  
Dr.Web StatD 255  
Dr.Web Updater 174  
drweb-configd 74

drweb-ctl 80  
drweb-ctl usage examples 111  
drweb-esagent 182  
drweb-filecheck 153  
drweb-httpd 186  
drweb-meshd 246  
drweb-netcheck 157  
drweb-netcheck: scanning cluster 164  
drweb-se 168  
drweb-smbspider-daemon 141  
drweb-snmpd 213  
drweb-spider 130  
drweb-statd 255  
drweb-update 174

### E

EICAR 62  
ESAgent: configuration 183

### F

fighting computer threats 262  
File access rights 20  
File permissions 20  
FileCheck: configuration 155  
Functions 10

### G

General configuration settings 77  
Generating certificates 271  
Getting Started 59  
GNU/Linux File System Monitor 63

### H

How to change settings 69  
How to Connect to the Centralized Protection Server 69  
How to install a key 69  
How to protect a server 69  
How to upgrade the product 69  
How to view log 69  
How to view settings 69  
HTTP API 191  
HTTPD: configuration 188

### I

Installation from .run package 31  
Installation from distribution 31





## Index

Installation from native packages 33  
Installation from universal packages 31  
Installing from the Repository 33  
Installing the anti-virus 29  
Installing the Product 30  
Integration with Samba 65  
Integration with SNMP Monitoring Systems 219  
Introduction 8  
Isolation 19

### K

Key File 59  
Known errors 274

### L

License key file 59  
Licensing 28  
LinuxSpider: configuration 134  
List of Supported Operating System Distributions 24

### M

Management Web Interface 116  
MeshD: configuration 250  
Mobile mode 21  
Modules 12  
Monitoring systems 219  
Monitoring via SNMP 219

### N

NetCheck: configuration 159

### O

Operating systems 24  
Operation modes 21

### P

Problems of SELinux 55  
Product files 47  
Product packages 47

### Q

Quarantine 19  
Quarantine Directories 19

### R

Registration 59

Removing the Product 42

### S

ScanEngine: configuration 172  
Section [ESAgent] 183  
Section [FileCheck] 155  
Section [HTTPD] 188  
section [LinuxSpider] 134  
Section [MeshD] 250  
Section [NetCheck] 159  
Section [Root] 77  
Section [ScanEngine] 172  
section [SMBSpider] 144  
Section [SNMPD] 215  
Section [StatD] 256  
Section [Update] 176  
SELinux Security 55  
SMB shared directories monitor 141  
SMBSpider: configuration 144  
SNMPD: configuration 215  
SplDer Guard 130  
SplDer Guard for SMB 141  
SSL CA 271  
SSL certificates 271  
SSL private keys 271  
Standalone mode 21  
Starting command-line tool 82  
Starting uninstaller 42  
StatD: configuration 256  
Structure of the product 12  
System Requirements 24

### T

Tasks 10  
Technical support 264  
Testing the Anti-virus 62  
The GNU/Linux file system monitor 130

### U

Uninstalling distribution 42  
Uninstalling from repository 43  
Uninstalling native packages 43  
Uninstalling the anti-virus 29  
Uninstalling the Product 42  
Update: configuration 176  
Upgrading components 37



# Index

Upgrading the Product 37

Upgrading to a Newer Version 38

## W

Ways to install 30

